

# **ArcSight Web™ User's Guide**

---

ArcSight Express v3.0  
Featuring ESM with CORR-Engine Storage

August 2011



## ArcSight Web™ User's Guide ArcSight Express™ v3.0

Copyright © 2001-2011 ArcSight, LLC. All rights reserved.

ArcSight and the ArcSight logo are registered trademarks of ArcSight in the United States and in some other countries. Where not registered, these marks and ArcSight Console, ArcSight ESM, ArcSight Express, ArcSight Manager, ArcSight Web, ArcSight Enterprise View, FlexConnector, ArcSight FraudView, ArcSight Identity View, ArcSight Interactive Discovery, ArcSight Logger, ArcSight NCM, SmartConnector, ArcSight Threat Detector, ArcSight TRM, and ArcSight Viewer, are trademarks of ArcSight, LLC. All other brands, products and company names used herein may be trademarks of their respective owners.

Follow this link to see a complete statement of ArcSight's copyrights, trademarks, and acknowledgements:

<http://www.arcsight.com/copyrightnotice>

The network information used in the examples in this document (including IP addresses and hostnames) is for illustration purposes only.

This document is ArcSight Confidential.

### Revision History

| Date       | Product Version       | Description   |
|------------|-----------------------|---|
| 07/27/2011 | ArcSight Express v3.0 | For ArcSight Web embedded in the Management Console |

Document template version: 1.0.2.9

### ArcSight Customer Support

|                       |   |
|-----------------------|---|
| Phone                 | 1-866-535-3285 (North America)<br>+ 44 (0)870 141 7487 (EMEA)                               |
| E-mail                | <a href="mailto:support@arcsight.com">support@arcsight.com</a>                              |
| Support Web Site      | <a href="http://www.arcsight.com/supportportal/">http://www.arcsight.com/supportportal/</a> |
| Protect 724 Community | <a href="https://protect724.arcsight.com">https://protect724.arcsight.com</a>               |

# Contents

---

|  |           |
|--|-----------|
| <b>Chapter 1: Welcome to ArcSight Web .....</b>        | <b>5</b>  |
| <b>Chapter 2: Navigating ArcSight Web .....</b>        | <b>7</b>  |
| Navigating the Home Page .....                         | 7         |
| Basic Navigation .....                                 | 8         |
| <b>Chapter 3: ArcSight Express Content .....</b>       | <b>11</b> |
| ArcSight Express Home Page .....                       | 12        |
| Recent Notifications .....                             | 12        |
| My Cases .....   | 12        |
| Dashboards .....                                       | 12        |
| Active Channels .....                                  | 12        |
| Getting Started Using ArcSight Express Content .....   | 13        |
| ArcSight Express Groups .....                          | 13        |
| Monitoring with ArcSight Express Active Channels ..... | 14        |
| Monitoring with ArcSight Express Dashboards .....      | 15        |
| Reporting with ArcSight Express Reports .....          | 16        |
| <b>Chapter 4: Using Active Channels .....</b>          | <b>17</b> |
| Opening Active Channels .....                          | 17        |
| Viewing Active Channels .....                          | 19        |
| Using Active Channel Headers .....                     | 19        |
| Using Active Channel Grids .....                       | 19        |
| Supported Expressions for Inline Filtering .....       | 21        |
| Inspecting Events .....                                | 22        |
| Event Inspector Header Features .....                  | 22        |
| Event Inspector Field Features .....                   | 23        |
| Show Details for Event Attributes .....                | 23        |
| Event Categories .....                                 | 23        |
| Event Data Fields .....                                | 30        |
| Audit Events .....                                     | 76        |
| Status Monitor Events .....                            | 82        |

---

|   |            |
|---|------------|
| <b>Chapter 5: Using Cases</b>                     | <b>93</b>  |
| Managing Cases                                    | 93         |
| Default Case Management Columns                   | 94         |
| Security Classification Default Letter Codes      | 94         |
| Creating Cases                                    | 95         |
| Initial Tab                                       | 95         |
| Follow Up Tab                                     | 97         |
| Final Tab   | 98         |
| Events Tab  | 99         |
| Attachments Tab                                   | 99         |
| Notes Tab   | 100        |
| <b>Chapter 6: Handling Notifications</b>          | <b>101</b> |
| <b>Chapter 7: Using Reports</b>                   | <b>103</b> |
| Running and Viewing Reports                       | 103        |
| Running and Saving Archived Reports               | 103        |
| Report Parameters                                 | 104        |
| Viewing Archived Reports                          | 105        |
| Downloading an Archived Report                    | 105        |
| Adding New Archived Reports                       | 105        |
| Deleting Archived Reports                         | 106        |
| Advanced Configuration for Report Performance     | 106        |
| Configurations for Large Reports                  | 106        |
| Configurations for Reports with Large Time Ranges | 107        |
| <b>Chapter 8: Monitoring Dashboards</b>           | <b>109</b> |
| Viewing and Managing Dashboards                   | 109        |
| Changing Dashboard Layouts                        | 109        |
| <b>Chapter 9: Using the Knowledge Base</b>        | <b>111</b> |
| <b>Chapter 10: Using Reference Pages</b>          | <b>113</b> |
| <b>Chapter 11: Setting Preferences</b>            | <b>115</b> |
| <b>Chapter 12: Custom Branding and Styling</b>    | <b>117</b> |

# Welcome to ArcSight Web

---

ArcSight Web is the web interface to monitoring and reporting features of ArcSight ESM for operators and analysts engaged in network perimeter and security monitoring. ArcSight Web for ArcSight Express v3.0 is presented as part of the Management Console. For more about the Management Console, see the *Management Console User's Guide*.

ArcSight Web offers opportunities for custom branding and styling.

To get started using the ArcSight Web interface, see the introduction to ["ArcSight Express Content" on page 11](#) if you have an ArcSight Express deployment.

See ["Navigating ArcSight Web" on page 7](#) for a quick tour of all ArcSight Web's features.



## Chapter 2

# Navigating ArcSight Web

---

Access the ArcSight Web server through whichever web browser you prefer: Internet Explorer 8.0+ or Firefox 3.6+. The ArcSight Web home URL is <https://hostname:9443/arcsight/app>, where *hostname* is the machine on which the web server is running.

[“Navigating the Home Page” on page 7](#)

[“Basic Navigation” on page 8](#)

## Navigating the Home Page

The ArcSight Web client opens to the Home display. From here you can easily reach everything the client offers.

The Home display's summaries are quick references and links to the most-appropriate or most-interesting security resources in your enterprise. The initial or default information in each group is configured by your ArcSight administrator. In the sections that offer a **Show** menu, you can choose **Start Up View** to see this default or **Personal Folder** to switch to resources selected by or assigned to you.

The information summarized in the Home display is identical to, although possibly a subset of, the same information managed through the ArcSight Console. It is simply presented in a browser-compatible format.

### Home

The Home link returns you to the home page from any other view.

### Dashboards

The Dashboards section lists a set of data monitor dashboards that expose selected analytical security information about your enterprise. Click a dashboard's name to open it.

### Reports

The Reports section lists available reports. Reports are captured views or summaries of data extrapolated from the ArcSight System by means of queries and trends. Reports communicate the state of your enterprise security. Click a report, set the parameters or accept the defaults (HTML or PDF), and click **Run Report**. You have the option of saving the Report results in a variety of file formats to your local system, or just viewing the results in the ArcSight Web window.

### Active Channels

Active Channels display the filtered events as they stream through the system. Click a channel to open it as a grid view in which you can inspect individual events. You can pause channels, and sort event columns in the grid.

### Cases







The Cases section summarizes currently tracked, event-related security situations by the area they fall into (rows) and the workflow-style stage they have reached (columns). Click a type and stage cell to see more detail.

### Recent Notifications

The Recent Notifications section summarizes ArcSight notifications by workflow-style categories. Click a category to see more detail.

## Basic Navigation

Use the Dashboards, Reports, Channels, Cases Notifications, and Knowledge Base links at the top of the display to go to those features. A link to **ArcSight Support** is also provided.

| Button  | Description   |
|---|---------------|
|    | Home          |
|   | Dashboards    |
|  | Reports       |
|  | Channels      |
|  | Cases         |
|  | Notifications |

The top bar also has the client's basic controls.

- Click **Help** to open this Help window. To visit previously viewed Help pages, you can use standard keyboard commands for **Back** and **Next**. For example, on most Web browsers running on Microsoft Windows systems, you can hit the **Backspace** key to show the previously viewed page (move backward in the History) and **Shift + Backspace** to move forward in the History of viewed pages. For more information on using the Help (including how to print topics and get a PDF), see [Chapter 3, About the Online Help, on page vii](#).
- Click **Options** to change your preferences concerning date and time formats, locale settings, active channel setup, and your password.
- Click **Logout** to leave the client and log in again, or browse elsewhere. If you leave the client idle for a period of time you may need to log in again because of an automatic security time-out.
- Click the ArcSight logo in the upper-left corner of the Home display to see version and licensing information.







# ArcSight Express Content

---

ArcSight Express is an Information and Event Management (SIEM) appliance that provides essential network perimeter and security monitoring tools combined with the Correlation Optimized Retention and Retrieval Engine (CORRE). ArcSight Express delivers an easy-to-deploy, enterprise-level security monitoring and response system through a series of coordinated resources, such as dashboards, rules, and reports included as part of ArcSight Express Content.

ArcSight Express content is designed to give you comprehensive operational function out of the box with minimal configuration.

These resources enable you to use the active channels and dashboards to monitor the network, use the case tracking tools to investigate and resolve issues, and use the reports to communicate the condition of the network to key stakeholders at all levels of the enterprise.

[“ArcSight Express Home Page” on page 12](#)

[“Getting Started Using ArcSight Express Content” on page 13](#)

[“Monitoring with ArcSight Express Active Channels” on page 14](#)

[“Reporting with ArcSight Express Reports” on page 16](#)

## ArcSight Express Home Page

The ArcSight Express home page displays a series of basic views designed to give you an overview of activity that concerns you. These views are described below.



### Recent Notifications

Recent notifications show the status of notifications generated by correlated events that concern you. To view the details of a notification, click any line item to go to the Notifications page. For more about notifications, see [“Handling Notifications” on page 101](#).

### My Cases

My cases show a snapshot of cases assigned to the user who is currently logged in. For details, click the cases icon to go to the Cases page. For more about cases, see [“Using Cases” on page 93](#).

### Dashboards

Dashboards show a selection of key dashboards. You can select among these views:

- **Start Up View:** The start-up view provides quick access to the Security Activity Statistics and Current Event Sources dashboards. These dashboards give you a comprehensive general view of the security state of your environment and the sources where the events are generated.
- **Recent Dashboards:** This view shows the last five dashboards you viewed to enable you to easily toggle among several dashboards without having to navigate to them in the Dashboard tab.

Click any of these links to display the dashboard itself.

### Active Channels

- **Start Up View:** The start-up view provides a link to the Correlated Alerts channel, which shows all events generated by rules. These events are considered to be events of interest that warrant attention.

- **Personal Folder:** This view contains active channels that you have modified and saved.
- **Recent Channels:** This view shows the last five active channels you viewed to enable you to easily toggle among several active channels without having to navigate to them in the active channels tab.

For more about the home page, see [“Navigating ArcSight Web” on page 7](#).

## Getting Started Using ArcSight Express Content

Whatever your role in the security operations center, you can get started right away using the ArcSight Express content.

### ArcSight Express Groups


ArcSight Express content is organized into the following device groups relevant to the function the content performs:

| Function            | Description   |
|---------------------|---|
| Cross-Device        | This group contains resources that monitor and report on functions that apply to multiple kinds of devices, such as login attempts, bandwidth usage, and configuration changes.                           |
| Anti-Virus          | This group contains resources that support monitoring and reporting on anti-virus activity, such as update status, virus activity, and configuration changes.   |
| Case Management     | This group contains resources that support monitoring and reporting on activity and notifications involving cases opened in ArcSight as a result of activity that warrants investigation.                 |
| Database            | This group contains resources that monitor and report on database activity, such as configuration changes, database logins, errors and warnings.  |
| Firewall            | This group contains resources that monitor and report on firewall activity, such as network logins and logouts, denied connections, bandwidth usage, and configuration changes.                           |
| Identity Management | This group contains resources that monitor and report on user activity, such as logins, user session durations, and configuration changes in order to identify who is doing what activity on the network. |
| IDS-IPS             | This group contains resources that monitor and report on activity involving Intrusion Detection and Prevention Systems, such as signature updates, alerts, and statistics.                                |
| Network             | This group contains resources that monitor and report on activity involving network infrastructure, including system up/down status, configuration changes, bandwidth usage, and login events.            |
| Operating System    | This group contains resources that monitor and report on activity involving operating systems, such as user logins, and user modification events.   |
| VPN                 | This group contains resources that monitor and report on activity involving VPN connections, including authentication errors, logins, and connection status.  |
| Vulnerabilities     | This group contains resources that monitor and report on exposed vulnerabilities by asset.  |

## Monitoring with ArcSight Express Active Channels

The active channels contain three major groups of channels:


- ArcSight Administration
- ArcSight Express
- Device Class Event Channels




The staple active channels in the ArcSight Express group are a good place to start for monitoring event flows. For instructions about how to use active channels, see [“Using Active Channels” on page 17](#).

## Monitoring with ArcSight Express Dashboards

The dashboards contain the ArcSight Administration and ArcSight Express groups. Explore the dashboards to find views you are interested in.



The example below shows the IDS-IPS dashboard, which summarizes the number of events from IDS and IPS systems. Click on any bar to view the details of the events represented in this bar in a channel.



For more about working with dashboards, see ["Monitoring Dashboards"](#) on page 109.

## Reporting with ArcSight Express Reports

The reports also contain the ArcSight Administration and ArcSight Express groups.


**Report Definitions**

- express's Reports
- Shared
  - ArcSight Administration
    - Connectors
    - ESM
  - ArcSight Express
    - Security Intelligence Status Report
    - Cross-Device
    - Anti-Virus
    - Case Management
    - Database
    - Firewall
    - Identity Management
    - IDS - IPS
    - Network
    - Operating System
    - VPN
    - Vulnerabilities

**ArcSight Administration**  
This group contains reports that communicate the health and performance of ArcSight ESM and its components.

**ArcSight Express**  
This group contains reports that provide detailed summaries of events by device type.

The Security Intelligence Status Report provides a summary of event counts and top events, attacks, targets, ports, and so on, as shown in the example below.



For more about working with reports, see [“Using Reports”](#) on page 103.



## Chapter 4

# Using Active Channels

---

The event information presented in the ArcSight Web active channel views is the same data presented in the Console. The web client makes channels accessible from anywhere on your enterprise network, or even outside a firewall.

Using active channels includes opening them, controlling their views, and drilling down into the individual events that channels collect.

[“Opening Active Channels” on page 17](#)



[“Viewing Active Channels” on page 19](#)

[“Inspecting Events” on page 22](#)

## Opening Active Channels

To open an active channel, click its name in the Active Channels section of the Home display, or click the Channels icon in the toolbar and choose a channel in the Active Channels resource tree. Channels you click in the Home display open directly, but channels you choose in the resource tree offer a setup page before opening.

Use the Open Active Channel setup display to adjust the timing, filter, and column-set parameters of the channel, if necessary. This display appears unless you have turned channel setup off (bypass channel setup) in the Channels panel of the Options display.

There is also an option to hide (collapse) the channel tree on the left panel when a channel is already running. By default, this tree remains in view. Click the Show  or Hide  buttons at the top of the left panel to show or hide the folder tree.

### Active Channel Parameters

| Option     | Description   |
|------------|---|
| Channel    | Read-only field that shows the channel name.  |
| Start Time | The relative or absolute time reference that begins the period in which to actively track the events in the channel. Edit the time expression or clear the <b>Date expression</b> check box to use an absolute date and time. |
| End Time   | The relative or absolute time reference that ends the period in which to actively track the events in the channel. Edit the time expression or clear the <b>Date expression</b> check box to use an absolute date and time.   |

| Option                           | Description  |
|----------------------------------|--|
| Evaluate parameters continuously | Choose whether the channel will show events that are qualified by Start and End times that are re-evaluated constantly while it is running (selected), or show only the events that qualify when the channel is first run (cleared).   |
| Use as Timestamp                 | Choose the event-timing phase that best supports your analysis. <b>End Time</b> represents the time the event ended, as reported by the device. <b>Manager Receipt Time</b> is the event's recorded arrival time at the ArcSight Manager.  |
| Field Set                        | <p>The Field Set you choose here determines which columns will show up in the active channel display. By default, a standard list of columns is shown in the channel.</p> <p>Choose an existing field set to control the selection and order of the columns in the grid or choose <b>More Choices</b> or click the plus sign (+) to open the Field Sets resource tree. The <b>None</b> option clears a field set and restores the channel to its original definition.</p> <p>Global variables make it possible to define a variable that derives particular values from existing data, then re-use it in multiple places wherever conditions can be expressed, and wherever fields can be selected. For more information about global variables, see <a href="#">"Global Variables" on page 441</a>, in the <i>ESM Console User Guide</i>.the Domain Field Sets topic</p>  |
| Filter Override                  | <p>You can use the Filter Override to narrow the event flow in the channel to only those events that satisfy conditions you specify here. You have these options for Filter Override:</p> <ul style="list-style-type: none"> <li>Simply choose an existing filter. You can choose a recently used filter from the drop-down menu, or navigate to other filters by clicking <b>More Choices</b> or clicking the plus sign (+) to override the default channel filter. (The <b>None</b> option clears a filter choices and restores the channel to its original definition.)</li> </ul> <p>Or</p> <ul style="list-style-type: none"> <li>Explicitly specify new filter conditions for the channel by using event attributes (field groups and fields) or an existing filter (MatchesFilter) as part of a condition.</li> </ul> <p>the Domain Field Sets topicYou can review the conditions of the filter in the active channel header (see <a href="#">"Using Active Channel Headers" on page 19</a>).</p> |

## Viewing Active Channels

This topic explains how to understand, change, and drill into the grid views of active channels.

### Using Active Channel Headers

Using active channels begins with reading and understanding their headers. Headers display the following information:

| Feature         | Usage  |
|-----------------|--|
| Name and Total  | The top line of the header shows the channel's name and the percentage of qualifying events that are currently loaded in the view.   |
| Time Span       | The Start Time and End Time show the chronological range of the channel.   |
| Evaluation      | This flag indicates whether the channel is set to evaluate events continuously as they are received, or only once when the channel opens. Click <b>Modify</b> to change this parameter.  |
| Filter          | This text describes the filter that limits what the channel shows.   |
| Priority Totals | On the right side of the header is a column of event-priority category totals. The figures are the number of events in those categories.   |
| Channel State   | The channel state box contains a play and pause button and a refresh progress bar. This display indicates whether the channel is running or paused, and if it is running, the progress of the next refresh cycle.  |
| Radar Display   | <p>The Radar display in active channel headers indicates the activity taking place in the entire channel (not just the current page). Its graphics represent units of time horizontally, and numbers of events in vertical bars segmented by Priority attribute-value counts. The time and quantity scales in the graphic automatically adjust to accommodate the scope of the channel. The broader the scope, the smaller the graphical units become.</p> <p>To focus the grid on the event of one period, click that bar in the display. To restore the display, click <b>Clear</b> at the right end of the bar. Your sorting choices in the grid affect the arrangement of the activity units in the Radar.</p> |
| Time Range      | The Displaying bar below the Radar display and above the grid header shows the time range of the events selected in the Radar display and reflected in the grid. If nothing is selected, the time range shows <b>All</b> .   |

### Using Active Channel Grids

Event grids display the individual events that active channels capture.

#### To page through a grid

Click the navigation buttons on the right side of the grid column header. The numbers represent specific pages, and the advance arrows go one step or all the way forward or back.

### To use field sets

Choose a named set of fields from the **Field Set** drop-down menu. The sets available are usually tailored to your enterprise. Note that the field-set variables found in the ArcSight Console are not available through ArcSight Web.

Choose the Field Set **Customize** option (if available) to temporarily add, remove, or rearrange the columns in the current grid. You can create one custom field set per channel.

the Domain Field Sets topic

### To sort a grid

Click any grid column heading to sort the whole view by that column. Each click toggles between ascending and descending. The default order of grids is usually determined by the End Time of events, as selected in the current active channel display.

### To filter a grid

To apply an inline filter, click **Inline Filter** in the grid header and choose an available value from the drop-down menus for one or more columns. This enables you to filter by values already available in the channel. Click **Apply** to put the filter into effect.


You can also filter by entering custom expressions into the text field for each column. To customize an inline filter, type a value in the text field above the column on which you want to filter, and click **Apply**. Supported expressions for custom filtering are shown in the table below.

## Supported Expressions for Inline Filtering

| Type                           | Supported Expressions and Examples  |
|--------------------------------|---|
| String-based Columns           | <p>The <a href="#">Contains</a> and <a href="#">StartsWith</a> operators are supported. The values for the operator must be in quotes.</p> <p><b>Examples:</b></p> <pre>Contains "Event" Contains "Event" OR Contains "Top" Contains "Web" AND Contains "denied" StartsWith "Web" StartsWith "Web" OR Contains "denied" StartsWith "Web" AND Contains "denied"</pre> <p>You can use OR and AND Boolean operators in between the expressions. The Column field name is implicitly used as the left-hand parameter.</p> |
| Integer and IP Address Columns | <p>The <a href="#">Between</a> operator is supported. The values in the <a href="#">Between</a> expression must be in quotes.</p> <p><b>Examples:</b></p> <pre>For the port column: Between("20", "80") For the IP address column: Between("10.0.0.1", "10.0.0.255") For priority column: Between("1", "2") OR Between("7", "8")</pre> <p>You can use OR and AND Boolean operators in between the expressions. The Column field name is implicitly used as the left-hand parameter.</p>                               |

### To add an event to a case

Select one or more event check boxes on the left, then click **Add to Case** to choose an existing or new case to add it to in the Cases resource tree. Click the **Existing case** radio button to add the events to the case you select in the tree. Click the **New case** radio button to name the case and add it at the currently selected point in your personal tree. Click **Add** to save the assignments and return to the grid.

To view the events associated with a case, click the Cases  navigation button at the top of the page, choose a case, and click the Events tab for that case. For more information, see [“Events Tab” on page 99](#) in [“Using Cases” on page 93](#).

### To change a grid's options

Click **Options** in the grid header to change the display's update frequency and its number of rows per page.

### To save a modified channel

Click **Save Channel As** in the channel header to add a modified channel to your personal folder in the Active Channels resource tree. In the Save Channel As dialog box, name the channel and click **Save**.

**To inspect an event**

Click any individual event in the grid to show that event in the Event Inspector as described in Inspecting Events.

## Inspecting Events

Use the Event Inspector display to examine the details of events that appear in active channels. To open the Event Inspector, click an event in an active channel's grid view. The Event Inspector shows the data fields and categories associated with the event you selected. Apart from these fields, the display has the features described below.

### Event Inspector Header Features

| Feature                       | Usage   |
|-------------------------------|---|
| Associated Articles           | If a knowledge base article exists for this event, the <b>View Articles</b> link will display the article from the Knowledge Base.  |
| Associated References         | If a reference page exists for this event, the <b>View References</b> link will display the reference page. Reference pages provide additional background on an event or a resource. These may be pre-populated by ArcSight, provided by vendors, or added by technologists in your organization.   |
| Additional Details            | Click this link to view <b>Additional Details</b> on the event, such as vendor and product information, event category information, reference pages, and vulnerability pages.   |
| View Event Context Report     | Click this link to run an <b>Event Context Report</b> that shows the events that occurred within a specified number of minutes (a window) before and after this event.  |
| View Rule Context Report      | Click this link to run a <b>Rule Context Report</b> that shows the events that occurred within a specified number of minutes (a window) before and after the current rule was invoked.  |
| Payload Viewer                | Click this link to view the payload for the event. The <b>Payload Viewer</b> option is available only if the event has a payload associated with it. A "payload" is information carried in the body of an event's network packet, as distinct from the packet's header data. Events will include payloads only if the associated SmartConnectors are configured to send events with payloads.       |
| View iDefense Incident Report | Click <b>View iDefense Incident Report</b> to view information about vulnerability IDs related to the event. This option is available only if you have VeriSign iDefense software installed and configured to interact with the Arcsight system, and if the selected event has a vulnerability ID associated with it. In that case, the iDefense report provides more details on the vulnerability. |
| Field Sets                    | Choose <b>Field Sets</b> to see a predefined set of event data fields rather than all fields. Use the <b>None</b> option to restore the default view.   |
| Hide Empty Rows               | By default, the <b>Hide Empty Rows</b> check box is checked, so the display isn't filled with unused fields. Clear the check box to see all fields, even if empty.  |



## Event Inspector Field Features

The values for fields in events are also links. Click these values to open new channels or to filter current channels using them.

| Option                                  | Use   |
|---|---|
| Create Channel<br>[Field Name = Value]  | Open a channel containing only those events that have matching values for the selected field.         |
| Create Channel<br>[Field Name != Value] | Open a channel that shows only those events that do not have a matching value for the selected event. |
| Add to Channel<br>[Attribute = Value]   | Add the attribute-value pair to the channel's filter (require that they match).                       |
| Add to Channel<br>[Attribute != Value]  | Exclude the attribute-value pair from the channel's filter (require that they do not match).          |

## Show Details for Event Attributes

View details for each attribute associated with an event.

- To view event attribute details inline, click the **Details** button () next to the attribute.
- To view event attribute details on a new Web page, click the **Show detail in a new page** button () next to the attribute.

## Event Categories

ESM uses six primary categories and a flexible set of supporting attributes to more precisely distinguish the events reported by SmartConnectors or generated internally by ArcSight Managers. These categories appear as a field in the Event Inspector.

These categories and attributes are designated by ArcSight, based on the information offered to SmartConnectors by sensors. Keep in mind that the applicability of a category always depends on the actual configuration of the environment.

The category groups are:

- **Object:** The physical or virtual object that was the focus of the event. (See [“Object Category” on page 24.](#))
- **Behavior:** The action taken on the object. (See [“Behavior Category” on page 25.](#))
- **Outcome:** An indication of whether the action succeeded on the object. (See [“Outcome Category” on page 27.](#))
- **Device Group:** The type of device from which the sensor reported the event. (See [“Device Group Category” on page 27.](#))
- **Technique:** The method used to apply the action to the object (i.e., the type of attack). (See [“Technique Category” on page 28.](#))
- **Significance:** A description of the security significance of the event from the reporting sensor's perspective. (See [“Significance Category” on page 30.](#))

## Object Category

| Object Category  | Description   |
|------------------|---|
| Host             | Any end-system on the network, such as a PDA, a Windows computer, or a Linux computer.  |
| Operating System | The system software that controls execution of computer programs and access to resources on a host.   |
| Application      | A software program that is not an integral part of the operating system.  |
| Service          | An application that normally executes at operating system startup. A service often accepts network connections.   |
| Database         | A database application.   |
| Backdoor         | An application, visible on a host, that listens for network connections and can give a non-authorized user control over that host.                        |
| DoS Client       | A host that is displaying an application that can participate in a (possibly distributed) denial-of-service attack.                                       |
| Peer to Peer     | An application that listens for, and establishes network connections to, other installations of the same application such as Kazaa, Morpheus, or Napster. |
| Virus            | A host that is displaying a replicating infection of a file that also executes other behaviors on the infected host.                                      |
| Worm             | A host that is displaying a self-replicating program that spreads itself automatically over the network from one computer to the next.                    |
| Resource         | An operating system resource that is characteristically limited in its supply.  |
| File             | A long-term storage mechanism (e.g., files, directories, hard disks, etc.).   |
| Process          | A single executable module that runs concurrently with other executable modules.  |
| Interface        | An interface to the network.  |
| Interface Tunnel | Packaging a lower network protocol layer within a higher layer such as IPSec Tunnel and HTTP tunneling.   |
| Registry         | The central configuration repository for the operating system and the applications. Application-specific information is not stored here.                  |
| CPU              | Events directed at this object relate to consumption or use of the overall processing power of the host.  |
| Memory           | Events directed at this object relate to consumption or use of the overall memory of the host.  |
| Network          | Events that cannot be clearly associated with a host's subitem. Events that involve transport, or many hosts on the same subnet.                          |



| Object Category |            | Description   |
|-----------------|------------|---|
| Actor           | Routing    | Routing related events such as BGP.   |
|                 | Switching  | Switching related events such as VLANs.   |
|                 | User       | A single human identity.  |
|                 | Group      | A named collection of users, such as an employee division or social group.                                      |
| Vector          |            | The replication path for a section of malicious code.   |
|                 | Virus      | A replicating infection of a file that also executes other behaviors on the infected host.                      |
|                 | Worm       | A self-replicating program that automatically spreads itself across the network, from one computer to the next. |
|                 | Backdoor   | An application that listens for network connections and can give a non-authorized user control over that host.  |
|                 | DoS Client | An application that will participate in a (possibly distributed) denial-of-service attack.                      |

### Behavior Category

| Behavior Category |        | Description   |
|-------------------|--------|---|
| Access            |        | Refers to accessing objects, as in reading.                           |
|                   | Start  | The start of an ongoing access, such as login.                        |
|                   | Stop   | The end of an ongoing access, such as logging out.                    |
| Authentication    |        | Actions that support authentication.                                  |
|                   | Add    | Adding new authentication credentials.                                |
|                   | Delete | Deleting authentication credentials.                                  |
|                   | Modify | Modifying authentication credentials.                                 |
|                   | Verify | Credential verification, such as when logins occur.                   |
| Authorization     |        | Authorization-related actions.  |
|                   | Add    | Adding a privilege for the associated object (for example, a user).   |
|                   | Delete | Removing a privilege for the associated object (for example, a user). |
|                   | Modify | Modifying the existing privileges for the associated user or entity.  |
|                   | Verify | An authorization check, such as a privilege check.                    |
| Communicate       |        | Transactions that occur over the wire.                                |

| Behavior Category | Description  |
|-------------------|--|
| Query             | Communicating a request to a service.  |
| Response          | Communicating a response to a request, from a service.   |
| Create            | Seeks to create resources, install applications or services, or otherwise cause a new instance of an object.   |
| Delete            | The reverse of creation events. Includes uninstalling applications, services, or similar activity.   |
| Execute           | Involves loading or executing code, booting or shutting systems down, and similar activity.  |
| Start             | The beginning of execution of an application or service. This event is clearly distinguished from a lone "Execute" attribute.  |
| Stop              | The termination of execution of an application or service. This event is clearly distinguished from a lone "Execute" attribute.  |
| Query             | A query sent to a specific entity - but not over the network such as when generating a report.   |
| Response          | The answer returned by an Execute/Query. For example, a report delivered back from an application, or status messages from applications.   |
| Modify            | Involves changing some aspect of an object.  |
| Content           | Changing the object's content, such as writing to or deleting from a file or database.   |
| Attribute         | Changing some attribute of an object, such as a file name, modification date, or create date.  |
| Configuration     | Changing an object's configuration. For example, application, operating system, or registry changes.   |
| Substitute        | Replacing files, upgrading software, or service or host failovers.   |
| Found             | Noticing an object or its state.   |
| Vulnerable        | An exploitable state that is characteristic of a particular hardware or software release.  |
| Misconfigured     | An exploitable state caused by a weak configuration or similar mishandling.  |
| Insecure          | An exploitable state that arises from poor management or implementation. For example, weak authentication, weak passwords, passwords passed in the clear, default passwords, or simplistically named accounts. |
| Exhausted         | The targeted object was found to be exhausted (for example, not enough file descriptors are available).  |

### Outcome Category

These attributes indicate the probable success or failure of the specified event, within an overall context. For example, the outcome of an event such as an "operation failed" error message can be reported as a "/Success" given that the operation can be presumed to have actually caused a failure. Another example would be an event that identifies a Code Red infection: on a host running Linux the outcome would be "/Failure" (Code Red is Windows-only) while the same event directed at a host with an unknown OS would be reported as an ["/Attempt](#).

| Outcome Category | Description   |
|------------------|---|
| Attempt          | The event occurred but its success or failure cannot be determined. |
| Failure          | The event can be reasonable presumed to have failed.                |
| Success          | The event can be reasonable presumed to have succeeded.             |

### Device Group Category

| Device Group Category        | Description  |
|------------------------------|--|
| Application                  | An application program.  |
| Assessment Tool              | A network- or host-based scanner that monitors issues such as vulnerability, configurations, and ports.              |
| Security Information Manager | A security-event processing correlation engine (such as the Manager). This "device" deals only in correlated events. |
| Firewall                     | A firewall.  |
| IDS                          | An intrusion-detection system.   |
| Network                      | A network-based intrusion-detection system.  |
| Host                         | A host-based intrusion-detection system.   |
| Antivirus                    | An anti-virus scanner.   |
| File Integrity               | A file-integrity scanner.  |
| Identity Management          | Identity management.   |
| Operating System             | An operating system.   |
| Network Equipment            | Network equipment.   |
| Router                       | A network device with routing (layer 3) capabilities.  |
| Switches                     | A network device with switching (layer 2) capabilities.  |
| VPN                          | A virtual private network.   |

## Technique Category

| Technique Category       | Description  |
|--------------------------|--|
| Traffic                  | An anomaly in the network traffic, such as non-RFC compliance.   |
| <b>Network Layer</b>     | Anomalies related to IP, ICMP, and other network-layer protocols.  |
| IP Fragment              | Fragmented IP packets.   |
| Man in the Middle        | A man-in-the-middle attack.  |
| Spoof                    | Spoofing a source or destination IP address.   |
| Flow                     | A problem in network-layer communication logic, such as an out-of-order IP fragment.   |
| <b>Transport Layer</b>   | Anomalies related to TCP, UDP, SSL, and other transport-layer protocols.   |
| Hijack                   | Hijacking a connection.  |
| Spoof                    | Spoofing a transport layer property such as a TCP port number, or an SSL entity.   |
| Flow                     | A problem in TCP connections or flows, such as a SYNACK without SYN, a sequence number mismatch, or time exceeded.   |
| <b>Application Layer</b> | Application-layer anomalies.   |
| Flow                     | A peer does not follow the order of commands.  |
| Syntax Error             | A syntax error in an application-layer command.  |
| Unsupported Command      | A command which does not exist or is not supported.  |
| Man in the Middle        | A man-in-the-middle attack on the application layer.   |
| Exploit                  |  |
| <b>Vulnerability</b>     | Exploiting a vulnerability such as a buffer overflow, code injection, or format string.  |
| Weak Configuration       | Exploitation of a weak configuration. This is something that could be remedied easily by changing the configuration of the service. Examples of a weak configuration are weak passwords, default passwords, insecure software versions, or open SMTP relays. |
| Privilege Escalation     | A user identity has received an increase in its user privileges.   |
| Directory Transversal    | A user identity is attempting to browse or methodically review directories for which it may not have appropriate privileges.   |
| <b>Brute Force</b>       | Brute-force attacks.   |
| Login                    | Continued trials for logins.   |
| URL Guessing             | Continued trials for URLs to access information or scripts.  |
| <b>Redirection</b>       | Redirecting an entity.   |

| Technique Category    | Description   |
|-----------------------|---|
| ICMP                  | ICMP redirects.   |
| DNS                   | Unauthorized DNS changes.   |
| Routing Protocols     | Attacks aimed at routing protocols such as BGP, RIP, and OSPF.  |
| IP                    | Redirection using the IP protocol (source routing).   |
| Application           | Redirection attacks on the application layer such as cross-site scripting, mail routing, or JavaScript spoofing.  |
| <b>Code Execution</b> | Either the execution or transmission of executable code, or the transmission of a distinctive response from executed code.  |
| Trojan                | The code in question is concealed within other code that serves as a Trojan Horse. In other words, it appears to be one thing (that is safe) but is really another (which is unsafe). |
| Application Command   | The code in question is intended to invoke an application command.  |
| Shell Command         | The code in question is intended to be executed in a shell.   |
| Worm                  | Code associated with a worm.  |
| Virus                 | Code associated with a virus.   |
| <b>Scan</b>           | Any type of scanning. A network, host, application, or operating system scan can be identified through the specified object.  |
| Port                  | Multiple ports are scanned.   |
| Service               | A service is scanned (for example, DoS client discovery, backdoors, RPC services, or scans for a specific application such as NMB).   |
| Host                  | Scanning for hosts on a network.  |
| IP Protocol           | A search for responding protocols. Note that TCP and UDP are not the only transport protocols available.  |
| Vulnerability         | A scan for vulnerabilities.   |
| DoS                   | A denial of service (DoS) attack is in progress.  |
| Information Leak      | Information leaking out of its intended environment such as mail messages leaking out, system file access, FTP data access, or web document access.                                   |
| Convert Channel       | Leakage was detected from a covert channel such as Loki.  |
| Policy                | Policy-related violations such as pornographic web site access.   |
| Breach                | A policy-related security breach occurred.  |
| Compliant             | A policy-compliant event occurred.  |

## Significance Category

| Significance Category | Description   |
|-----------------------|---|
| Compromise            | A potentially compromising event occurred.                                      |
| Hostile               | A malicious event has happened or is happening.                                 |
| Informational         | Events considered worthy of inspection; for example, those produced by polling. |
| Error                 | An execution problem.   |
| Warning               | A possible problem.   |
| Alert                 | A situational problem that requires immediate attention.                        |
| Normal                | Ordinary or expected activity that is significant only for forensic purposes.   |
| Recon                 | Relates to scans and other reconnaissance activity.                             |
| Suspicious            | A potentially malicious event occurred.   |

## Event Data Fields

The security monitoring devices report events that are collected, filtered, and formatted by ArcSight SmartConnectors and passed to Managers for analysis. The events that appear in your client are composed of several data fields, each of which has its own characteristics.

Event data fields fall into the groups shown below. Most groups have several attributes.

- Connector
- Attacker
- Category
- Destination
- Device
- Device Custom
- Event
- Event Annotation
- File
- Final Device
- Flex
- Manager
- Old File
- Original Agent
- Request
- Source
- Target
- Threat

## Connector

This category falls into the device-to-Manager information chain. The chain begins at **Device**, which is the actual network hardware that senses an event. In cases where data is concentrated or otherwise pre-processed, it may be passed to a trusted reporting **Final Device** before reaching an **Original Agent** (agents are also known as SmartConnectors). Although the Original Agent is usually the only connector, if the data passes up through a Manager hierarchy the chain will include handling by **Connector** stages that are the ArcSight Manager SmartConnectors that facilitate Manager-to-Manager connections.

| Group     | Label          | Script Alias           | Data Type  | Default Turbo Level | Description   |
|-----------|----------------|------------------------|------------|---------------------|---|
| Connector | Address        | connectorAddress       | IP address | 1                   | The IP address of the device hosting the SmartConnector.  |
| Connector | Asset ID       | connectorAssetId       | Resource   | 1                   | The asset that represents the device hosting the SmartConnector.  |
| Connector | Asset Name     | connectorAssetName     | String     | 1                   | The connector's asset name.   |
| Connector | Asset Resource | connectorAssetResource | Resource   | 1                   | The connector resource.   |
| Connector | Descriptor ID  | connectorDescriptorId  | ID         | 1                   | The connector descriptor.   |
| Connector | DNS Domain     | connectorDnsDomain     | String     | 1                   | The Domain Name Service domain name associated with the device hosting the SmartConnector.                                    |
| Connector | Host Name      | connectorHostName      | String     | 1                   | The name of the device hosting the SmartConnector.  |
| Connector | ID             | connectorId            | String     | 1                   | The identifier associated with the SmartConnector configuration resource. The format is connectorID(1)   connectorID(2)   ... |
| Connector | MAC Address    | connectorMacAddress    | MacAddress | 1                   | The MAC address associated with the SmartConnector (which may or may not be the MAC address of the host device.)              |

| Group     | Label                       | Script Alias                      | Data Type                      | Default Turbo Level | Description  |
|-----------|-----------------------------|-----------------------------------|--------------------------------|---------------------|--|
| Connector | Name                        | connectorName                     | String                         | 1                   | The user-supplied name of the associated SmartConnector configuration resource.  |
| Connector | NT Domain                   | connectorNtDomain                 | String                         | 1                   | The Windows NT domain associated with the device hosting the SmartConnector.   |
| Connector | Receipt Time                | connectorReceiptTime              | DateTime                       | 2                   | The time the event arrived at the SmartConnector.  |
| Connector | Severity                    | connectorSeverity                 | Connector Severity Enumeration | 1                   | The normalized ArcSight form of the event severity value provided by the SmartConnector.   |
| Connector | Time Zone                   | connectorTimeZone                 | String                         | 1                   | The time zone reported by the device hosting the SmartConnector (as TLA).  |
| Connector | Time Zone Offset            | connectorTimeZoneOffset           | Integer                        | 1                   | The time zone reported by the device hosting the SmartConnector (shown as a UTC offset). Note that device times may be less accurate than other sources. |
| Connector | Translated Address          | connectorTranslatedAddress        | IP address                     | 1                   | If network address translation is an issue, this is the translated IP address of the device hosting the SmartConnector.                                  |
| Connector | Translated Zone             | connectorTranslatedZone           | Zone                           | 1                   | If network address translation is an issue, this is the Network Zone associated with the translated IP address of the device hosting the SmartConnector. |
| Connector | Translated Zone External ID | connectorTranslatedZoneExternalID | String                         | 1                   | See the common set of resource attributes.   |



| Group     | Label                        | Script Alias                       | Data Type | Default Turbo Level | Description   |
|-----------|------------------------------|------------------------------------|-----------|---------------------|---|
| Connector | Translated Zone ID           | connectorTranslatedZoneID          | String    | 1                   | See the common set of resource attributes.  |
| Connector | Translated Zone Name         | connectorTranslatedZoneName        | String    | 1                   | See the common set of resource attributes. Returns the name from the URI. It assumes that the name is always the last field of the URI. |
| Connector | Translated Zone Reference ID | connectorTranslatedZoneReferenceID | ID        | 1                   | See the common set of resource attributes. Returns the unique descriptor ID for this reference.   |
| Connector | Translated Zone Resource     | connectorTranslatedZoneResource    | Resource  | 1                   | See the common set of resource attributes. Locates the resource described by this reference.  |
| Connector | Translated Zone URI          | connectorTranslatedZoneURI         | String    | 1                   | See the common set of resource attributes.  |
| Connector | Type                         | connectorType                      | String    | 1                   | A description of the type of SmartConnector that reported the event.  |
| Connector | Version                      | connectorVersion                   | String    | 1                   | The software revision number of the SmartConnector that reported the event  |
| Connector | Zone                         | connectorZone                      | Zone      | 1                   | The network zone in which the device hosting this SmartConnector resides.   |
| Connector | Zone External ID             | connectorZoneExternalID            | String    | 1                   | See the common set of resource attributes.  |
| Connector | Zone ID                      | connectorZoneID                    | String    | 1                   | See the common set of resource attributes.  |
| Connector | Zone Name                    | connectorZoneName                  | String    | 1                   | See the common set of resource attributes.  |
| Connector | Zone Reference ID            | connectorZoneReferenceID           | ID        | 1                   | See the common set of resource attributes.  |

| Group     | Label         | Script Alias          | Data Type | Default Turbo Level | Description                                |
|-----------|---------------|-----------------------|-----------|---------------------|--|
| Connector | Zone Resource | connectorZoneResource | Resource  | 1                   | See the common set of resource attributes. |
| Connector | Zone URI      | connectorZoneURI      | String    | 1                   | Returns the URI for this reference.        |

## Attacker

| Group    | Label          | Script Alias          | Data Type     | Default Turbo Level | Description  |
|----------|----------------|-----------------------|---------------|---------------------|--|
| Attacker | Address        | attackerAddress       | IP address    | 1                   | The IP address of the device hosting the attacker.                                   |
| Attacker | Asset ID       | attackerAssetId       | Resource      | 2                   | The asset that represents the device hosting the attacker.                           |
| Attacker | Asset Name     | attackerAssetName     | String        | 2                   | The name of the asset that represents the device hosting the attacker.               |
| Attacker | Asset Resource | attackerAssetResource | Resource      | 2                   | See the common set of resource attributes  |
| Attacker | DNS Domain     | attackerDnsDomain     | String        | 2                   | The Domain Name Service domain name associated with the device hosting the attacker. |
| Attacker | FQDN           | attackerFqdn          | String        | 2                   | The fully qualified domain name associated with the device hosting the attacker.     |
| Attacker | Geo            | attackerGeo           | GeoDescriptor | 1                   | See the common set of geographical attributes.                                       |

| Group    | Label                | Script Alias              | Data Type   | Default Turbo Level | Description  |
|----------|----------------------|---------------------------|-------------|---------------------|--|
| Attacker | Geo Country Code     | attackerGeoCountryCode    | String      | 1                   | See the common set of geographical attributes.   |
| Attacker | Geo Country Flag URL | attackerGeoCountryFlagUrl | String      | 1                   | See the common set of geographical attributes.   |
| Attacker | Geo Country Name     | attackerGeoCountryName    | String      | 1                   | See the common set of geographical attributes.   |
| Attacker | Geo Descriptor ID    | attackerGeoDescriptorId   | ID          | 1                   | See the common set of geographical attributes.   |
| Attacker | Geo Latitude         | attackerGeoLatitude       | Double      | 1                   | See the common set of geographical attributes.   |
| Attacker | Geo Location Info    | attackerGeoLocationInfo   | String      | Location            | See the common set of geographical attributes.   |
| Attacker | Geo Longitude        | attackerGeoLongitude      | Double      | 1                   | See the common set of geographical attributes.   |
| Attacker | Geo Postal Code      | attackerGeoPostalCode     | String      | 1                   | See the common set of geographical attributes.   |
| Attacker | Geo Region Code      | attackerGeoRegionCode     | String      | 1                   | See the common set of geographical attributes.   |
| Attacker | Host Name            | attackerHostName          | String      | 2                   | The name of the device hosting the attacker.   |
| Attacker | MAC Address          | attackerMacAddress        | MAC address | 2                   | The MAC address associated with the source of the attack (which may or may not be the MAC address of the host device). |
| Attacker | NT Domain            | attackerNtDomain          | String      | 2                   | The Windows NT domain associated with the device hosting the attacker.   |
| Attacker | Port                 | attackerPort              | Integer     | 1                   | The network port associated with the source of the attack.   |

| Group    | Label                        | Script Alias                      | Data Type  | Default Turbo Level | Description  |
|----------|------------------------------|-----------------------------------|------------|---------------------|--|
| Attacker | Process Name                 | attackerProcessName               | String     | 2                   | The name of process associated with the source of the attack.  |
| Attacker | Service Name                 | attackerServiceName               | String     | 2                   | The name of service associated with the source of the attack.  |
| Attacker | Translated Address           | attackerTranslatedAddress         | IP address | 1                   | If network address translation is an issue, this is the translated IP address of the device hosting the attacker.                                  |
| Attacker | Translated Port              | attackerTranslatedPort            | Integer    | 1                   | If network address translation is an issue, this is the translated source port associated with the attack. This can happen in a NAT environment.   |
| Attacker | Translated Zone              | attackerTranslatedZone            | Zone       | 1                   | If network address translation is an issue, this is the network zone associated with the translated IP address of the device hosting the attacker. |
| Attacker | Translated Zone External ID  | attackerTranslatedZoneExternalID  | String     | 1                   | See the common set of resource attributes.   |
| Attacker | Translated Zone ID           | attackerTranslatedZoneID          | String     | 1                   | See the common set of resource attributes.   |
| Attacker | Translated Zone Name         | attackerTranslatedZoneName        | String     | 1                   | See the common set of resource attributes. It is assumed that the name is always the last field of the URI.  |
| Attacker | Translated Zone Reference ID | attackerTranslatedZoneReferenceID | ID         | 1                   | See the common set of resource attributes.   |
| Attacker | Translated Zone Resource     | attackerTranslatedZoneResource    | Resource   | 1                   | See the common set of resource attributes.   |
| Attacker | Translated Zone URI          | attackerTranslatedZoneURI         | String     | 1                   | See the common set of resource attributes.   |

| Group    | Label             | Script Alias            | Data Type | Default Turbo Level | Description   |
|----------|-------------------|-------------------------|-----------|---------------------|---|
| Attacker | User ID           | attackerUserId          | String    | 2                   | The identifier associated with the OS or application of the attacker, at the source of the attack.          |
| Attacker | User Name         | attackerUserName        | String    | 2                   | The name associated with the attacker, at the source of the attack.   |
| Attacker | User Privileges   | attackerUserPrivileges  | String    | 2                   | The user-privilege associated with the attacker, at the source of the attack.                               |
| Attacker | Zone              | attackerZone            | Zone      | 1                   | The network zone in which the attacker's device resides.  |
| Attacker | Zone External ID  | attackerZoneExternalID  | String    | 1                   | See the common set of resource attributes.  |
| Attacker | Zone ID           | attackerZoneID          | String    | 1                   | See the common set of resource attributes.  |
| Attacker | Zone Name         | attackerZoneName        | String    | 1                   | See the common set of resource attributes. It is assumed that the name is always the last field of the URI. |
| Attacker | Zone Reference ID | attackerZoneReferenceID | ID        | 1                   | See the common set of resource attributes.  |
| Attacker | Zone Resource     | attackerZoneResource    | Resource  | 1                   | See the common set of resource attributes.  |
| Attacker | Zone URI          | attackerZoneURI         | String    | 1                   | See the common set of resource attributes.  |

## Category

See ["Event Categories" on page 23](#) for a complete description of the event category types and their supporting attributes.

| Group    | Label               | Script Alias              | Data Type | Default Turbo Level | Description  |
|----------|---------------------|---------------------------|-----------|---------------------|--|
| Category | Behavior            | categoryBehavior          | String    | 1                   | Describes the action taken with or by the object.                                    |
| Category | Custom Format Field | categoryCustomFormatField | String    | 1                   | Describes the content of a custom formatted field, if present.                       |
| Category | Descriptor ID       | categoryDescriptorId      | ID        | 1                   | The unique ID for the sensor that reported the event                                 |
| Category | Device Group        | categoryDeviceGroup       | String    | 1                   | Describes the type of event this event represents.                                   |
| Category | Object              | categoryObject            | String    | 1                   | Describes the physical or virtual object that was the focus of the event             |
| Category | Outcome             | categoryOutcome           | String    | 1                   | Indicates whether the action was successfully applied to the object.                 |
| Category | Significance        | categorySignificance      | String    | 1                   | Characterizes the event from a network-intrusion-detection perspective.              |
| Category | Technique           | categoryTechnique         | String    | 1                   | Describes the method used to apply the action to the object.                         |
| Category | Tuple Description   | categoryTupleDescription  | String    | 1                   | The prose description of the event category, assembled from the category components. |

## Destination

| Group       | Label                | Script Alias                 | Data Type     | Default Turbo Level | Description   |
|-------------|----------------------|------------------------------|---------------|---------------------|---|
| Destination | Address              | destinationAddress           | IP address    | 1                   | The IP address of the destination device.   |
| Destination | Asset ID             | destinationAssetId           | Resource      | 2                   | The asset that represents the device that was the network traffic's destination.        |
| Destination | Asset Name           | destinationAssetName         | String        | 2                   | See the common set of resource attributes.  |
| Destination | Asset Resource       | destinationAssetResource     | Resource      | 2                   | See the common set of resource attributes.  |
| Destination | DNS Domain           | destinationDnsDomain         | String        | 2                   | The Domain Name Service domain name associated with the user at the destination device. |
| Destination | FQDN                 | destinationFqdn              | String        | 2                   | The fully qualified domain name associated with the destination device.                 |
| Destination | Geo                  | destinationGeo               | GeoDescriptor |                     | See the common set of geographical attributes.  |
| Destination | Geo Country Code     | destinationGeoCountryCode    | String        | 1                   | The country code.   |
| Destination | Geo Country Flag URL | destinationGeoCountryFlagUrl | String        | 1                   | The country flag.   |
| Destination | Geo Country Name     | destinationGeoCountryName    | String        | 1                   | The country name.   |
| Destination | Geo Descriptor ID    | destinationGeoDescriptorId   | ID            | 1                   | See the common set of geographical attributes.  |
| Destination | Geo Latitude         | destinationGeoLatitude       | Double        | 1                   | The destination latitude.   |
| Destination | Geo Location Info    | destinationGeoLocationInfo   | String        | 1                   | The destination location.   |
| Destination | Geo Longitude        | destinationGeoLongitude      | Double        | 1                   | The destination longitude.  |

| Group       | Label              | Script Alias                   | Data Type   | Default Turbo Level | Description   |
|-------------|--------------------|--------------------------------|-------------|---------------------|---|
| Destination | Geo Postal Code    | destinationGeoPostalCode       | String      | 1                   | The destination postal code.  |
| Destination | Geo Region Code    | destinationGeoRegionCode       | String      | 1                   | See the common set of geographical attributes.  |
| Destination | Host Name          | destinationHostName            | String      | 2                   | The name of the destination device.   |
| Destination | MAC Address        | destinationMacAddress          | MAC address | 2                   | The MAC address associated with the network traffic's destination (which may or may not be the MAC address of the host device).         |
| Destination | NT Domain          | destinationNtDomain            | String      | 2                   | The Windows NT domain associated with the destination device.   |
| Destination | Port               | destinationPort                | Integer     | 1                   | The network port associated with the network traffic's destination.   |
| Destination | Process Name       | destinationProcessName         | String      | 2                   | The name of process associated with the network traffic's destination.  |
| Destination | Service Name       | destinationServiceName         | String      | 2                   | The name of service associated with the network traffic's destination.  |
| Destination | Translated Address | destinationTranslatedAddresses | IP address  | 1                   | If network address translation is an issue, this is the translated IP address of the device that was the network traffic's destination. |
| Destination | Translated Port    | destinationTranslatedPort      | Integer     | 1                   | If network address translation is an issue, this is the translated source port associated with the attack.                              |



| Group       | Label                       | Script Alias                         | Data Type | Default Turbo Level | Description  |
|-------------|-----------------------------|--------------------------------------|-----------|---------------------|--|
| Destination | Translated Zone             | destinationTranslatedZone            | Zone      | 1                   | If network address translation is an issue, this is the network zone associated with the translated IP address of the device at the network's traffic's destination. |
| Destination | Translated Zone External ID | destinationTranslatedZoneExternalID  | String    | 1                   | See the common set of resource attributes.   |
| Destination | Translated Zone ID          | destinationTranslatedZoneID          | String    | 1                   | See the common set of resource attributes.   |
| Destination | Translated Zone Name        | destinationTranslatedZoneName        | String    | 1                   | See the common set of resource attributes.   |
| Destination | Translated Zone Reference   | destinationTranslatedZoneReferenceID | ID        | 1                   | See the common set of resource attributes.   |
| Destination | Translated Zone Resource    | destinationTranslatedZoneResource    | Resource  | 1                   | See the common set of resource attributes.   |
| Destination | Translated Zone URI         | destinationTranslatedZoneURI         | String    | 1                   | See the common set of resource attributes.   |
| Destination | User ID                     | destinationUserId                    | String    | 2                   | The OS- or application-based identifier associated with the user at the network traffic's destination.   |
| Destination | User Name                   | destinationUserName                  | String    | 2                   | The name associated with the user at the network traffic's destination.  |
| Destination | User Privileges             | destinationUserPrivileges            | String    | 2                   | The privileges accorded the user at the network traffic destination.   |
| Destination | Zone                        | destinationZone                      | Zone      | 1                   | The network zone in which the destination device resides.  |
| Destination | Zone External ID            | destinationZoneExternalID            | String    | 1                   | See the common set of resource attributes.   |

| Group       | Label             | Script Alias               | Data Type | Default Turbo Level | Description  |
|-------------|-------------------|----------------------------|-----------|---------------------|--|
| Destination | Zone ID           | destinationZoneID          | String    | 1                   | See the common set of resource attributes.   |
| Destination | Zone Name         | destinationZoneName        | String    | 1                   | See the common set of resource attributes.   |
| Destination | Zone Reference ID | destinationZoneReferenceID | ID        | 1                   | Returns the unique descriptor ID for this reference. This is populated only if this reference has been stored and uniquely identified in the database. |
| Destination | Zone Resource     | destinationZoneResource    | Resource  | 1                   | See the common set of resource attributes.   |
| Destination | Zone URI          | destinationZoneURI         | String    | 1                   | See the common set of resource attributes.   |

### Device

This category falls into the device-to-Manager information chain. The chain begins at **Device**, which is the actual network hardware that senses an event. In cases where data is concentrated or otherwise pre-processed, it may be passed to a trusted reporting **Final Device** before reaching an **Original Connector**. Although the **Original Connector** is usually the only connector, if the data passes up through a Manager hierarchy the chain will include handling by **Connector** stages that are the Manager SmartConnectors that facilitate Manager-to-Manager connections.

| Group  | Label    | Script Alias  | Data Type  | Default Turbo Level | Description  |
|--------|----------|---------------|------------|---------------------|--|
| Device | Action   | deviceAction  | String     | 2                   | The device-specific description of some activity associated with the event |
| Device | Address  | deviceAddress | IP address | 1                   | The IP address of the device hosting the sensor.                           |
| Device | Asset ID | deviceAssetId | Resource   | 1                   | The asset that represents the device hosting the sensor.                   |

| Group  | Label             | Script Alias           | Data Type                  | Default Turbo Level | Description  |
|--------|-------------------|------------------------|----------------------------|---------------------|--|
| Device | Asset Name        | deviceAssetName        | String                     | 1                   | The name of the device.  |
| Device | Asset Resource    | deviceAssetResource    | Resource                   | 1                   | The resource the asset represents.   |
| Device | Descriptor ID     | deviceDescriptorId     | ID                         | 1                   | The asset's descriptor ID.   |
| Device | Direction         | deviceDirection        | DeviceDirectionEnumeration | 2                   | Whether the traffic was inbound or outbound.   |
| Device | DNS Domain        | deviceDnsDomain        | String                     | 1                   | The Domain Name Service domain name associated with the device hosting the sensor.                                     |
| Device | Domain            | deviceDomain           | String                     | 2                   | The specific domain containing the sensor device associated with the event   |
| Device | Event Category    | deviceEventCategory    | String                     | 2                   | The category description included with the event as reported by the device.  |
| Device | Event Class ID    | deviceEventClassId     | String                     | 2                   | The device-specific identifier associated with this type of event  |
| Device | External ID       | deviceExternalId       | String                     | 1                   | The external identifier associated with this sensor device, if provided by the vendor.                                 |
| Device | Facility          | deviceFacility         | String                     | 1                   | The sensor submodule that reported the event   |
| Device | Host Name         | deviceHostName         | String                     | 1                   | The name of the device hosting the sensor.   |
| Device | Inbound Interface | deviceInboundInterface | String                     | 1                   | The NIC card on the sensor device that received the network traffic associated with the event.                         |
| Device | MAC Address       | deviceMacAddress       | MAC address                | 1                   | The MAC address associated with the source of the attack (which may or may not be the MAC address of the host device). |

| Group  | Label              | Script Alias            | Data Type  | Default Turbo Level | Description   |
|--------|--------------------|-------------------------|------------|---------------------|---|
| Device | NT Domain          | deviceNtDomain          | String     | 1                   | The Windows NT domain associated with the device hosting the sensor.  |
| Device | Outbound Interface | deviceOutboundInterface | String     | 1                   | The NIC card on the sensor device that transmitted the network traffic associated with the event.               |
| Device | Payload ID         | devicePayloadId         | String     | 2                   | The internal identifier associated with a payload object associated with this event.                            |
| Device | Process Name       | deviceProcessName       | String     | 1                   | The sensor device process that reported the event.  |
| Device | Product            | deviceProduct           | String     | 1                   | The product name of the sensor device.  |
| Device | Receipt Time       | deviceReceiptTime       | DateTime   | 2                   | The time when the sensor device observed the event.   |
| Device | Severity           | deviceSeverity          | String     | 2                   | The device-specific assessment of event severity. This assessment varies with the device involved.              |
| Device | Time Zone          | deviceTimeZone          | String     | 1                   | The time zone reported by the device hosting the sensor device (shown as TLA).                                  |
| Device | Time Zone Offset   | deviceTimeZoneOffset    | Integer    | 1                   | The time zone reported by the device hosting this sensor device (shown as an offset from UTC).                  |
| Device | Translated Address | deviceTranslatedAddress | IP address | 1                   | If network address translation is an issue, this is the translated IP address of the device hosting the sensor. |

| Group  | Label                       | Script Alias                    | Data Type | Default Turbo Level | Description  |
|--------|-----------------------------|---------------------------------|-----------|---------------------|--|
| Device | Translated Zone             | deviceTranslatedZone            | Zone      | 1                   | If network address translation is an issue, this is the network zone associated with the translated IP address of the device hosting the sensor.       |
| Device | Translated Zone External ID | deviceTranslatedZoneExternalID  | String    | 1                   | See the common set of resource attributes.   |
| Device | Translated Zone ID          | deviceTranslatedZoneID          | String    | 1                   | See the common set of resource attributes.   |
| Device | Translated Zone Name        | deviceTranslatedZoneName        | String    | 1                   | See the common set of resource attributes.   |
| Device | Translated Zone Resource    | deviceTranslatedZoneReferenceID | ID        | 1                   | Returns the unique descriptor ID for this reference. This is populated only if this reference has been stored and uniquely identified in the database. |
| Device | Translated Zone Resource    | deviceTranslatedZoneResource    | Resource  | 1                   | See the common set of resource attributes.   |
| Device | Translated Zone URI         | deviceTranslatedZoneURI         | String    | 1                   | See the common set of resource attributes.   |
| Device | Vendor                      | deviceVendor                    | String    | 1                   | The vendor who manufactured or sold the sensor device.   |
| Device | Version                     | deviceVersion                   | String    | 1                   | The software revision number of the sensor device.   |
| Device | Zone                        | deviceZone                      | Zone      | 1                   | The network zone in which the sensor's device resides.   |
| Device | Zone External ID            | deviceZoneExternalID            | String    | 1                   | See the common set of resource attributes.   |
| Device | Zone ID                     | deviceZoneID                    | String    | 1                   | See the common set of resource attributes.   |

| Group  | Label             | Script Alias          | Data Type | Default Turbo Level | Description  |
|--------|-------------------|-----------------------|-----------|---------------------|--|
| Device | Zone Name         | deviceZoneName        | String    | 1                   | See the common set of resource attributes.   |
| Device | Zone Reference ID | deviceZoneReferenceID | ID        | 1                   | Returns the unique descriptor ID for this reference. This is populated only if this reference has been persisted and given a unique database identifier. |
| Device | Zone Resource     | deviceZoneResource    | Resource  | 1                   | See the common set of resource attributes.   |
| Device | Zone URI          | deviceZoneURI         | String    | 1                   | See the common set of resource attributes.   |

### Device Custom

| Group         | Label         | Script Alias             | Data Type | Default Turbo Level | Description              |
|---------------|---------------|--------------------------|-----------|---------------------|--------------------------|
| Device Custom | Date1         | deviceCustomDate1        | DateTime  | 2                   | First customDate         |
| Device Custom | Date1 Label   | deviceCustomDate1Label   | String    | 2                   | First customDate label   |
| Device Custom | Date2         | deviceCustomDate2        | DateTime  | 2                   | Second customDate        |
| Device Custom | Date2 Label   | deviceCustomDate2Label   | String    | 2                   | Second customDate label  |
| Device Custom | Descriptor ID | deviceCustomDescriptorId | ID        | 2                   | Custom descriptor ID     |
| Device Custom | Number1       | deviceCustomNumber1      | Long      | 2                   | First customNumber       |
| Device Custom | Number1 Label | deviceCustomNumber1Label | String    | 2                   | First customNumber label |

| Group         | Label         | Script Alias             | Data Type | Default Turbo Level | Description               |
|---------------|---------------|--------------------------|-----------|---------------------|---------------------------|
|               |               |                          |           |                     |                           |
| Device Custom | Number2       | deviceCustomNumber2      | Long      | 2                   | Second customNumber       |
| Device Custom | Number2 Label | deviceCustomNumber2Label | String    | 2                   | Second customNumber label |
| Device Custom | Number3       | deviceCustomNumber3      | Long      | 2                   | Third customNumber        |
| Device Custom | Number3 Label | deviceCustomNumber3Label | String    | 2                   | Third customNumber label  |
| Device Custom | String1       | deviceCustomString1      | String    | 2                   | First customString        |
| Device Custom | String1 Label | deviceCustomString1Label | String    | 2                   | First customString label  |
| Device Custom | String2       | deviceCustomString2      | String    | 2                   | Second customString       |
| Device Custom | String2 Label | deviceCustomString2Label | String    | 2                   | Second customString label |
| Device Custom | String3       | deviceCustomString3      | String    | 2                   | Third customString        |
| Device Custom | String3 Label | deviceCustomString3Label | String    | 2                   | Third customString label  |
| Device Custom | String4       | deviceCustomString4      | String    | 2                   | Fourth customString       |
| Device Custom | String4 Label | deviceCustomString4Label | String    | 2                   | Fourth customString label |
| Device Custom | String5       | deviceCustomString5      | String    | 2                   | Fifth customString        |
| Device Custom | String5 Label | deviceCustomString5Label | String    | 2                   | Fifth customString label  |
| Device Custom | String6       | deviceCustomString6      | String    | 2                   | Sixth customString        |
| Device Custom | String6 Label | deviceCustomString6Label | String    | 2                   | Sixth customString label  |

## Event

| Group | Label                   | Script Alias           | Data Type           | Default Turbo Level | Description   |
|-------|-------------------------|------------------------|---------------------|---------------------|---|
|       |                         |                        |                     |                     |   |
| Event | Additional Data         | additionalData         | AdditionalData      | 3                   | Reference to additional data.   |
| Event | Aggregated Event Count  | (not applicable)       | (not applicable)    | n / a               | A derived field that reports the number of actual events collectively represented by the event in question.                           |
| Event | Application Protocol    | applicationProtocol    | String              | 2                   | A description of the application layer protocol. May be set, but defaults to Target Port lookup (FTP).                                |
| Event | Base Event Count        | baseEventCount         | Integer             | 1                   | The number of events upon which this event is based (e.g., type == BASE ACTION).  |
| Event | Base Event IDs          | baseEventIds           | ID                  | 2                   | The array of event IDs that contributed to generating this correlation event. This is populated only in correlated events.            |
| Event | Bytes In                | bytesIn                | Integer             | 2                   | Number of bytes transferred into the device during this transaction (this would typically be associated with entries in HTTP logs).   |
| Event | Bytes Out               | bytesOut               | Integer             | 2                   | Number of bytes transferred out of the device during this transaction (this would typically be associated with entries in HTTP logs). |
| Event | Concentrator Connectors | concentratorConnectors | ConnectorDescriptor | 2                   | The chain of concentrators that forwarded the event. This is not yet exposed in the user interface.                                   |



| Group | Label                  | Script Alias        | Data Type        | Default Turbo Level | Description  |
|-------|------------------------|---------------------|------------------|---------------------|--|
| Event | Concentrator Devices   | concentratorDevices | DeviceDescriptor | 2                   | The list of devices that concentrate events, if applicable. This is not exposed in the user interface.   |
| Event | Correlated Event Count | (not applicable)    | (not applicable) | n / a               | A derived field that reports the number of actual events that had to occur to cause a correlation event to occur.                                      |
| Event | Crypto Signature       | cryptoSignature     | String           | 2                   | The signature of the event object (meaning in this alert, as opposed to the occurrence represented by the event). Not yet supported.                   |
| Event | Customer               | customer            | Customer         | 1                   | The "customer" resource reference. This is used in MSSP environments to describe the client or divisional entity to whom the event applies.            |
| Event | Customer External ID   | customerExternalID  | String           | 1                   | Returns the external ID for this reference.  |
| Event | Customer ID            | customerID          | String           | 1                   | Returns the ID for the resource in this resource reference.  |
| Event | Customer Name          | customerName        | String           | 1                   | Returns the name from the URI, which is always assumed to be the last field of the URI.  |
| Event | Customer Reference ID  | customerReferenceID | ID               | 1                   | Returns the unique descriptor ID for this reference. This is populated only if this reference has been stored and uniquely identified in the database. |
| Event | Customer Resource      | customerResource    | Resource         | 1                   | Locates the resource described by this reference.  |

| Group | Label                  | Script Alias         | Data Type | Default Turbo Level | Description  |
|-------|------------------------|----------------------|-----------|---------------------|--|
|       |                        |                      |           |                     |  |
| Event | Customer URI           | customerURI          | String    | 1                   | Returns the URI for this reference.  |
| Event | End Time               | endTime              | DateTime  | 1                   | Event ends (defaults to deviceReceiptTime).  |
| Event | Event ID               | eventId              | ID        | 1                   | Long value identifying an event.   |
| Event | External ID            | externalId           | String    | 2                   | A reference to the ID used by an external device. This is useful for tracking devices that create events that contain references to these IDs (e.g., ManHunt). |
| Event | Generator              | generator            | null      | 1                   | The "generator" resource reference (the resource that generated the event. This is the subcomponent in the connector that generates the event.                 |
| Event | Generator External ID  | generatorExternalID  | String    | 1                   | Returns the external ID for this reference.  |
| Event | Generator ID           | generatorID          | String    | 1                   | Returns the ID for the resource in this resource reference.  |
| Event | Generator Name         | generatorName        | String    | 1                   | Returns the name from the URI, which is always assumed to be the last field of the URI.  |
| Event | Generator Reference ID | generatorReferenceID | ID        | 1                   | Returns the unique descriptor ID for this reference. This is populated only if this reference has been stored and uniquely identified in the database.         |
| Event | Generator Resource     | generatorResource    | Resource  | 1                   | Locates the resource described by this reference.  |
| Event | Generator URI          | generatorURI         | String    | 1                   | Returns the URI for this reference.  |

| Group | Label          | Script Alias | Data Type              | Default Turbo Level | Description  |
|-------|----------------|--------------|------------------------|---------------------|--|
|       |                |              |                        |                     |  |
| Event | Locality       | locality     | LocalityEnumeration    | 2                   | The locality associated with the event.  |
| Event | Message        | message      | String                 | 2                   | A brief comment associated with this event.  |
| Event | Name           | name         | String                 | 1                   | An arbitrary string that describes this type of event. Event details included in other parts of an event shouldn't be used in the event name.  |
| Event | Originator     | originator   | OriginatorEnumeration  | 1                   | Holds the value of Source Destination. This determines whether source and destination should be translated to attacker and target or they should be inversed.  |
| Event | Persistence    | persistence  | PersistenceEnumeration | 2                   | There are two states: Persisted or Transient. Events default to being Transient and are marked as Persisted as soon as they reach the Batch Alert Persistor or when they are loaded by the Alert Broker.   |
| Event | Raw Event      | rawEvent     | String                 | 1                   | The original log entry reported by the sensor (synthesized when the sensor does not log to a file or text stream).   |
| Event | Rule Thread ID | ruleThreadId | String                 | 2                   | A single rule can issue many events, based on several triggers, starting with On First Event and ending with On Threshold Timeout. All such events for a single Rule and a single Group By tuple will be marked with the same identifier using this attribute. |

| Group | Label                      | Script Alias             | Data Type       | Default Turbo Level | Description  |
|-------|----------------------------|--------------------------|-----------------|---------------------|--|
|       |                            |                          |                 |                     |  |
| Event | Session ID                 | sessionId                | Long            | 2                   | Tags for events created by a correlation simulation, as part of a particular simulation.   |
| Event | Start Time                 | startTime                | DateTime        | 1                   | Event begins (defaults to deviceReceiptTime).  |
| Event | Transport Protocol         | transportProtocol        | String          | 1                   | The format of the transmitted data associated with the event from a network transport perspective (e.g., TCP, UDP).  |
| Event | Type                       | type                     | TypeEnumeration | 1                   | One of the event types: Base, Correlation, Aggregation, or Action.   |
| Event | Vulnerability              | vulnerability            | Vulnerability   | 2                   | The vulnerability resource that represents the vulnerability or exposure that may be exploited by this event and is present on the targeted device according to our network model. |
| Event | Vulnerability External ID  | vulnerabilityExternalID  | String          | 2                   | Returns the external ID for this reference.  |
| Event | Vulnerability ID           | vulnerabilityID          | String          | 2                   | Returns the ID for the resource in this resource reference.  |
| Event | Vulnerability Name         | vulnerabilityName        | String          | 2                   | Returns the name from the URI, which is always assumed to be the last field of the URI.  |
| Event | Vulnerability Reference ID | vulnerabilityReferenceID | ID              | 2                   | Returns the unique descriptor ID for this reference. This is populated only if this reference has been stored and uniquely identified in the database.                             |
| Event | Vulnerability Resource     | vulnerabilityResource    | Resource        | 2                   | Locates the resource described by this reference.  |

| Group | Label             | Script Alias     | Data Type | Default Turbo Level | Description                         |
|-------|-------------------|------------------|-----------|---------------------|-------------------------------------|
| Event | Vulnerability URI | vulnerabilityURI | String    | 2                   | Returns the URI for this reference. |

## Event Annotation

| Group            | Label                   | Script Alias                        | Data Type     | Default Turbo Level | Description  |
|------------------|-------------------------|-------------------------------------|---------------|---------------------|--|
| Event Annotation | Audit Trail             | eventAnnotationAuditTrail           | String        | 2                   | The text log of annotation changes. Changes are recorded as sets of comma-separated-value entries. |
| Event Annotation | Comment                 | eventAnnotationComment              | String        | 2                   | A text description of the event or associated information.   |
| Event Annotation | End Time                | eventAnnotationEndTime              | DateTime      | 2                   | The timestamp for an eventannotation.  |
| Event Annotation | Event ID                | eventAnnotationEventId              | ID            | 2                   | The event ID for the annotation event.   |
| Event Annotation | Flags                   | eventAnnotationFlags                | FlagsValueSet | 2                   | The state of the collaboration flags.  |
| Event Annotation | Manager Receipt Time    | eventAnnotationManagerReceiptTime   | DateTime      | 2                   | The time the Manager received the event annotation.  |
| Event Annotation | Modification Time       | eventAnnotationModificationTime     | DateTime      | 2                   | The time the annotation was modified.  |
| Event Annotation | Modified By             | eventAnnotationModifiedBy           | User          | 2                   | The user ID of the person who last edited this annotation.   |
| Event Annotation | Modified By External ID | eventAnnotationModifiedByExternalID | String        | 2                   | Returns the external ID for this reference.  |

| Group            | Label                    | Script Alias                         | Data Type | Default Turbo Level | Description  |
|------------------|--------------------------|--------------------------------------|-----------|---------------------|--|
| Event Annotation | Modified By ID           | eventAnnotationModifiedByID          | String    | 2                   | Returns the ID for the resource in this resource reference.  |
| Event Annotation | Modified By Name         | eventAnnotationModifiedByName        | String    | 2                   | Returns the name from the URI (the last field of the URI).   |
| Event Annotation | Modified By Reference ID | eventAnnotationModifiedByReferenceID | ID        | 2                   | Returns the unique descriptor ID for this reference. This is populated only if this reference has been stored and uniquely identified in the database. |
| Event Annotation | Modified By Resource     | eventAnnotationModifiedByResource    | Resource  | 2                   | Locates the resource described by this reference.  |
| Event Annotation | Modified By URI          | eventAnnotationModifiedByURI         | String    | 2                   | Returns the URI for this reference.  |
| Event Annotation | Stage                    | eventAnnotationStage                 | Stage     | 2                   | The current disposition of the event. This enables annotation workflow.  |
| Event Annotation | Stage Event ID           | eventAnnotationStageEventId          | ID        | 2                   | The reference to an internal identifier for another event. It is used by 'Mark Similar'.   |
| Event Annotation | Stage External ID        | eventAnnotationStageExternalID       | String    | 2                   | Returns the external ID for this reference.  |
| Event Annotation | Stage ID                 | eventAnnotationStageID               | String    | 2                   | Returns the ID for the resource in this resource reference.  |
| Event Annotation | Stage Name               | eventAnnotationStageName             | String    | 2                   | Returns the name from the URI, which is always assumed to be the last field of the URI.  |
| Event Annotation | Stage Reference ID       | eventAnnotationStageReferenceID      | ID        | 2                   | Returns the unique descriptor ID for this reference. This is populated only if this reference is stored and uniquely identified in the database.       |

| Group            | Label                   | Script Alias                        | Data Type | Default Turbo Level | Description  |
|------------------|-------------------------|-------------------------------------|-----------|---------------------|--|
| Event Annotation | Stage Resource          | eventAnnotationStageResource        | Resource  | 2                   | Locates the resource described by this reference.  |
| Event Annotation | Stage Update Time       | eventAnnotationStageUpdateTime      | ID        | 2                   | The time of the last stage change (in UTC).  |
| Event Annotation | Stage URI               | eventAnnotationStageURI             | String    | 2                   | Returns the URI for this reference.  |
| Event Annotation | Stage User              | eventAnnotationStageUser            | User      | 2                   | The user associated with the current stage. This implements assignment within workflow.  |
| Event Annotation | Stage User External ID  | eventAnnotationStageUserExternalID  | String    | 2                   | Returns the external ID for this reference.  |
| Event Annotation | Stage User ID           | eventAnnotationStageUserID          | String    | 2                   | Returns the ID for the resource in this resource reference.  |
| Event Annotation | Stage User Name         | eventAnnotationStageUserName        | String    | 2                   | Returns the name from the URI, which is always assumed to be the last field of the URI.  |
| Event Annotation | Stage User Reference ID | eventAnnotationStageUserReferenceID | ID        | 2                   | Returns the unique descriptor ID for this reference. This is populated only if this reference is stored and uniquely identified in the database. |
| Event Annotation | Stage User Resource     | eventAnnotationStageUserResource    | Resource  | 2                   | Locates the resource described by this reference.  |
| Event Annotation | Stage User URI          | eventAnnotationStageUserURI         | String    | 2                   | Returns the URI for this reference.  |
| Event Annotation | Version                 | eventAnnotationVersion              | Integer   | 2                   | The editing version number which increments with each change. This enables optimistic locking.   |

## File

| Group | Label             | Script Alias         | Data Type | Default Turbo Level | Description  |
|-------|-------------------|----------------------|-----------|---------------------|--|
| File  | Create Time       | fileCreateTime       | DateTime  | 2                   | The time the file was created (in UTC).                                |
| File  | Hash              | fileHash             | String    | 2                   | The hashcode associated with the file's contents (e.g., MD5).          |
| File  | ID                | fileId               | String    | 2                   | The external identifier associated with the file.                      |
| File  | Modification Time | fileModificationTime | DateTime  | 2                   | The time the file was last changed (in UTC).                           |
| File  | Name              | fileName             | String    | 2                   | The name of the file.  |
| File  | Path              | filePath             | String    | 2                   | The directory path to the file in the file system.                     |
| File  | Permission        | filePermission       | String    | 2                   | The user permissions associated with the file (sensor specific).       |
| File  | Size              | fileSize             | Long      | 2                   | The size of the file's contents (typically in bytes; sensor specific). |
| File  | Type              | fileType             | String    | 2                   | The type of file contents (sensor specific).                           |



### Final Device

This category falls into the device-to-Manager information chain. The chain begins at **Device**, which is the actual network hardware that senses an event. In cases where data is concentrated or otherwise pre-processed, it may be passed to a trusted reporting **Final Device** before reaching an **Original Connector**. Although the **Original Connector** is usually the only connector, if the data passes up through a Manager hierarchy the chain will include handling by **Connector** stages that are the Manager SmartConnectors that facilitate Manager-to-Manager connections.

| Group        | Label          | Script Alias             | Data Type  | Default Turbo Level | Description   |
|--------------|----------------|--------------------------|------------|---------------------|---|
| Final Device | Address        | finalDeviceAddress       | IP address | 2                   | The IP address of the trusted reporting device.   |
| Final Device | Asset ID       | finalDeviceAssetId       | Resource   | 2                   | The asset that represents the trusted reporting device.   |
| Final Device | Asset Name     | finalDeviceAssetName     | String     | 2                   | The name of the trusted reporting device.   |
| Final Device | Asset Resource | finalDeviceAssetResource | Resource   | 2                   | The resource represented by the trusted reporting device.   |
| Final Device | Descriptor ID  | finalDeviceDescriptorId  | ID         | 2                   | The descriptor ID of the trusted reporting device.  |
| Final Device | DNS Domain     | finalDeviceDnsDomain     | String     | 2                   | The Domain Name Service domain name associated with the trusted reporting device.   |
| Final Device | External ID    | finalDeviceExternalId    | String     | 2                   | The external ID for the trusted reporting device, if provided by the vendor.  |
| Final Device | Facility       | finalDeviceFacility      | String     | 2                   | A facility or capability of a device. This accommodates concentrators (e.g., like syslog, which has a concept of device logging for "parts" of a device). |
| Final Device | Host Name      | finalDeviceHostName      | String     | 2                   | The host name of the trusted reporting device.  |

| Group        | Label              | Script Alias                   | Data Type   | Default Turbo Level | Description   |
|--------------|--------------------|--------------------------------|-------------|---------------------|---|
| Final Device | Inbound Interface  | finalDeviceInboundInterface    | String      | 2                   | The NIC card on the sensor device that received the network traffic associated with the event.  |
| Final Device | MAC address        | finalDeviceMacAddress          | MAC address | 2                   | The MAC address associated with the trusted reporting device.   |
| Final Device | NT Domain          | finalDeviceNtDomain            | String      | 2                   | The Windows NT domain associated with the trusted reporting device.   |
| Final Device | Outbound Interface | finalDeviceOutboundInterface   | String      | 2                   | The NIC card on the trusted reporting device.   |
| Final Device | Process Name       | finalDeviceProcessName         | String      | 2                   | The process name of the trusted reporting device.   |
| Final Device | Product            | finalDeviceProduct             | String      | 2                   | The product name of the trusted reporting device.   |
| Final Device | Time Zone          | finalDeviceTimeZone            | String      | 2                   | The time zone reported by the trusted reporting device.   |
| Final Device | Time Zone Offset   | finalDeviceTimeZoneOffset      | Integer     | 2                   | Returns the raw time-zone offset for the trusted reporting device. Note that connector and device times are not always reliably accurate.       |
| Final Device | Translated Address | finalDeviceTranslatedAddresses | IP address  | 2                   | If network address translation is an issue, this is the translated IP address of the trusted reporting device.                                  |
| Final Device | Translated Zone    | finalDeviceTranslatedZone      | Zone        | 2                   | If network address translation is an issue, this is the network zone associated with the translated IP address of the trusted reporting device. |

| Group        | Label                        | Script Alias                         | Data Type | Default Turbo Level | Description  |
|--------------|------------------------------|--------------------------------------|-----------|---------------------|--|
| Final Device | Translated Zone External ID  | finalDeviceTranslatedZoneExternalID  | String    | 2                   | Returns the external ID for this reference.  |
| Final Device | Translated Zone ID           | finalDeviceTranslatedZoneID          | String    | 2                   | Returns the ID for the resource in this resource reference.  |
| Final Device | Translated Zone Name         | finalDeviceTranslatedZoneName        | String    | 2                   | Returns the name from the URI, which is always assumed to be the last field of the URI.  |
| Final Device | Translated Zone Reference ID | finalDeviceTranslatedZoneReferenceID | ID        | 2                   | Returns the unique descriptor ID for this reference. This is populated only if this reference has been stored and uniquely identified in the database. |
| Final Device | Translated Zone Resource     | finalDeviceTranslatedZoneResource    | Resource  | 2                   | Locates the resource described by this reference.  |
| Final Device | Translated Zone URI          | finalDeviceTranslatedZoneURI         | String    | 2                   | Returns the URI for this reference.  |
| Final Device | Vendor                       | finalDeviceVendor                    | String    | 2                   | Device vendor.   |
| Final Device | Version                      | finalDeviceVersion                   | String    | 2                   | The software revision number of the trusted reporting device.  |
| Final Device | Zone                         | finalDeviceZone                      | Zone      | 2                   | The network zone in which the trusted reporting device resides.  |
| Final Device | Zone External ID             | finalDeviceZoneExternalID            | String    | 2                   | Returns the external ID for this reference.  |
| Final Device | Zone ID                      | finalDeviceZoneID                    | String    | 2                   | Returns the ID for the resource in this resource reference.  |
| Final Device | Zone Name                    | finalDeviceZoneName                  | String    | 2                   | Returns the name from the URI, which is always assumed to be the last field of the URI.  |

| Group        | Label             | Script Alias               | Data Type | Default Turbo Level | Description  |
|--------------|-------------------|----------------------------|-----------|---------------------|--|
| Final Device | Zone Reference ID | finalDeviceZoneReferenceID | ID        | 2                   | Returns the unique descriptor ID for this reference. This is populated only if this reference has been stored and uniquely identified in the database. |
| Final Device | Zone Resource     | finalDeviceZoneResource    | Resource  | 2                   | Locates the resource described by this reference.  |
| Final Device | Zone URI          | finalDeviceZoneURI         | String    | 2                   | Returns the URI for this reference.  |

## Flex

| Group | Label         | Script Alias     | Data Type | Default Turbo Level | Description                     |
|-------|---------------|------------------|-----------|---------------------|---------------------------------|
| Flex  | Date1         | flexDate1        | DateTime  | 2                   | First flexDate.                 |
| Flex  | Date1 Label   | flexDate1Label   | String    | 2                   | Label of first flexDate.        |
| Flex  | Number1       | flexNumber1      | Long      | 2                   | First flexNumber.               |
| Flex  | Number1 Label | flexNumber1Label | String    | 2                   | Label of the first FlexNumber.  |
| Flex  | Number2       | flexNumber2      | Long      | 2                   | Second flexNumber.              |
| Flex  | Number2 Label | flexNumber2Label | String    | 2                   | Label of the second FlexNumber. |
| Flex  | String1       | flexString1      | String    | 2                   | First flexString                |
| Flex  | String1 Label | flexString1Label | String    | 2                   | Label of the first FlexString.  |
| Flex  | String2       | flexString2      | String    | 2                   | Second flexString.              |
| Flex  | String2 Label | flexString2Label | String    | 2                   | Label of the second FlexString. |

## Manager

| Group   | Label        | Script Alias       | Data Type | Default Turbo Level | Description   |
|---------|--------------|--------------------|-----------|---------------------|---|
| Manager | Receipt Time | managerReceiptTime | DateTime  | 1                   | The time at which the current Manager first received the event. |

## Old File

| Group    | Label             | Script Alias            | Data Type | Default Turbo Level | Description  |
|----------|-------------------|-------------------------|-----------|---------------------|--|
| Old File | Create Time       | oldFileCreateTime       | DateTime  | 2                   | The time the file was created (in UTC).                                |
| Old File | Hash              | oldFileHash             | String    | 2                   | The hashcode associated with the file's contents (e.g., MD5).          |
| Old File | ID                | oldFileId               | String    | 2                   | The external identifier associated with the file.                      |
| Old File | Modification Time | oldFileModificationTime | DateTime  | 2                   | The time the file was last changed (in UTC).                           |
| Old File | Name              | oldFileName             | String    | 2                   | The file's name.   |
| Old File | Path              | oldFilePath             | String    | 2                   | The directory path to the file in the file system.                     |
| Old File | Permission        | oldFilePermission       | String    | 2                   | The user permissions associated with the file (sensor specific).       |
| Old File | Size              | oldFileSize             | Long      | 2                   | The size of the file's contents (typically in bytes; sensor specific). |
| Old File | Type              | oldFileType             | String    | 2                   | The type of the file's contents (sensor specific).                     |

### Original Connector

This category falls into the device-to-Manager information chain. The chain begins at **Device**, which is the actual network hardware that senses an event. In cases where data is concentrated or otherwise pre-processed, it may be passed to a trusted reporting **Final Device** before reaching an **Original Connector**. Although the **Original Connector** is usually the only connector, if the data passes up through a Manager hierarchy the chain will include handling by **Connector** stages that are the Manager SmartConnectors that facilitate Manager-to-Manager connections.

| Group              | Label          | Script Alias                   | Data Type  | Default Turbo Level | Description  |
|--------------------|----------------|--------------------------------|------------|---------------------|--|
| Original Connector | Address        | originalConnectorAddress       | IP address | 2                   | The IP address of the device hosting the first reporting SmartConnector.                                   |
| Original Connector | Asset ID       | originalConnectorAssetID       | Resource   | 2                   | The asset that represents the device hosting the first reporting SmartConnector.                           |
| Original Connector | Asset Name     | originalConnectorAssetName     | String     | 2                   | The first reporting connector's asset name.  |
| Original Connector | Asset Resource | originalConnectorAssetResource | Resource   | 2                   | The first reporting connector's resource.  |
| Original Connector | Descriptor ID  | originalConnectorDescriptorId  | ID         | 2                   | The first reporting connector's descriptor.  |
| Original Connector | DNS Domain     | originalConnectorDnsDomain     | String     | 2                   | The Domain Name Service domain name associated with the device hosting the first reporting SmartConnector. |
| Original Connector | Host Name      | originalConnectorHostName      | String     | 2                   | The name of the device hosting the first reporting SmartConnector.   |
| Original Connector | ID             | originalConnectorId            | String     | 2                   | The ID of the connector. The format is connectorId(1) connectorId(2) ...                                   |

| Group              | Label                       | Script Alias                              | Data Type   | Default Turbo Level | Description  |
|--------------------|-----------------------------|---|-------------|---------------------|--|
| Original connector | MAC address                 | originalconnectorMacAddresses             | MAC address | 2                   | The MAC address associated with the first reporting Smartconnector (which may or may not be the MAC address of the host device.)   |
| Original connector | Name                        | originalconnectorName                     | String      | 2                   | User-supplied name of the first reporting connector.   |
| Original connector | NT Domain                   | originalconnectorNtDomain                 | String      | 2                   | The Windows NT domain associated with the device hosting the first reporting Smartconnector.   |
| Original connector | Time Zone                   | originalconnectorTimeZone                 | String      | 2                   | The time zone reported by the device hosting the first reporting Smartconnector.   |
| Original connector | Time Zone Offset            | originalconnectorTimeZoneOffset           | Integer     | 2                   | Returns the raw time-zone offset for the first reporting connector's time zone. Note that device and connector times may not be reliably accurate.                       |
| Original connector | Translated Address          | originalconnectorTranslatedAddress        | IP address  | 2                   | If network address translation is an issue, this is the translated IP address of the device hosting the first reporting Smartconnector.                                  |
| Original connector | Translated Zone             | originalconnectorTranslatedZone           | Zone        | 2                   | If network address translation is an issue, this is the Network Zone associated with the translated IP address of the device hosting the first reporting Smartconnector. |
| Original connector | Translated Zone External ID | originalconnectorTranslatedZoneExternalID | String      | 2                   | Returns the external ID for this reference.  |

| Group              | Label                        | Script Alias                               | Data Type | Default Turbo Level | Description  |
|--------------------|------------------------------|--|-----------|---------------------|--|
| Original connector | Translated Zone ID           | originalconnectorTranslatedZoneID          | String    | 2                   | Returns the ID for the resource in this resource reference.  |
| Original connector | Translated Zone Name         | originalconnectorTranslatedZoneName        | String    | 2                   | Returns the name from the URI, which is always assumed to be the last field of the URI.  |
| Original connector | Translated Zone Reference ID | originalconnectorTranslatedZoneReferenceID | ID        | 2                   | Returns the unique descriptor ID for this reference. This is populated only if this reference has been stored and uniquely identified in the database. |
| Original connector | Translated Zone Resource     | originalconnectorTranslatedZoneResource    | Resource  | 2                   | Locates the resource described by this reference.  |
| Original connector | Translated Zone URI          | originalconnectorTranslatedZoneURI         | String    | 2                   | Returns the URI for this reference.  |
| Original connector | Type                         | originalconnectorType                      | String    | 2                   | A string that describes the type of the first reporting connector. This is not the same as the device type.  |
| Original connector | Version                      | originalconnectorVersion                   | String    | 2                   | The software revision number of the Smartconnector that first reported the event.  |
| Original connector | Zone                         | originalconnectorZone                      | Zone      | 2                   | The network zone in which the device hosting the first reporting Smartconnector resides.   |
| Original connector | Zone External ID             | originalconnectorZoneExternalID            | String    | 2                   | Returns the external ID for this reference.  |
| Original connector | Zone ID                      | originalconnectorZoneID                    | String    | 2                   | Returns the ID for the resource in this resource reference.  |
| Original connector | Zone Name                    | originalconnectorZoneName                  | String    | 2                   | Returns the name from the URI, which is always assumed to be the last field of the URI.  |



| Group              | Label             | Script Alias                     | Data Type | Default Turbo Level | Description   |
|--------------------|-------------------|----------------------------------|-----------|---------------------|---|
| Original connector | Zone Reference ID | originalconnectorZoneReferenceID | ID        | 2                   | Returns the unique descriptor ID for this reference. This is populated only if this reference has been stored and is uniquely identified in the database. |
| Original connector | Zone Resource     | originalconnectorZoneResource    | Resource  | 2                   | Locates the resource described by this reference.   |
| Original connector | Zone URI          | originalconnectorZoneURI         | String    | 2                   | Returns the URI for this reference.   |

## Request

| Group   | Label              | Script Alias             | Data Type | Default Turbo Level | Description   |
|---------|--------------------|--------------------------|-----------|---------------------|---|
| Request | Client Application | requestClientApplication | String    | 2                   | The client application (such as a web browser) used to issue the request.                             |
| Request | Client Application | requestClientApplication | String    | 2                   | A description of the client application used to initiate this request, e.g., the HTTP User connector. |
| Request | Context            | requestContext           | String    | 2                   | A description of the content from which the request originated, e.g., the HTTP Referrer.              |
| Request | Cookies            | requestCookies           | String    | 2                   | Cookie data offered by the client application as part of the request.                                 |

| Group   | Label         | Script Alias        | Data Type | Default Turbo Level | Description   |
|---------|---------------|---------------------|-----------|---------------------|---|
| Request | Method        | requestMethod       | String    | 2                   | The style of the request, i.e., for an HTTP request this could be PUT or GET.                       |
| Request | Protocol      | requestProtocol     | String    | 2                   | The communication protocol used when issuing the request.   |
| Request | URL           | requestUrl          | String    | 2                   | A universal resource locator associated with the event.   |
| Request | URL Authority | requestUrlAuthority | String    | 2                   | The URL component used for authentication and authorization.  |
| Request | URL File Name | requestUrlFileName  | String    | 2                   | The URL component that refers to the file containing the resource.                                  |
| Request | URL Host      | requestUrlHost      | String    | 2                   | The URL component that specifies the host device where the resource resides.                        |
| Request | URL Port      | requestUrlPort      | Integer   | 2                   | The URL component that specifies the port to contact on the host device where the resource resides. |
| Request | URL Query     | requestUrlQuery     | String    | 2                   | The URL component that specifies the query to use to request the resource.                          |

## Source

| Group  | Label                | Script Alias            | Data Type     | Default Turbo Level | Description   |
|--------|----------------------|-------------------------|---------------|---------------------|---|
|        |                      |                         |               |                     |   |
| Source | Address              | sourceAddress           | IP address    | 1                   | The IP address of the source device.  |
| Source | Asset ID             | sourceAssetId           | Resource      | 2                   | The asset that represents the device that was the network traffic's source.   |
| Source | Asset Name           | sourceAssetName         | String        | 2                   | See the common set of resource attributes.  |
| Source | Asset Resource       | sourceAssetResource     | Resource      | 2                   | See the common set of resource attributes.  |
| Source | DNS Domain           | sourceDnsDomain         | String        | 2                   | The Domain Name Service domain name associated with the user at the source device.  |
| Source | FQDN                 | sourceFqdn              | String        | 2                   | The fully qualified domain name associated with the source device. This has no value if either the host name or DNS domain are without a value. |
| Source | Geo                  | sourceGeo               | GeoDescriptor | 1                   | The geographical information.   |
| Source | Geo Country Code     | sourceGeoCountryCode    | String        | 1                   | Country Code.   |
| Source | Geo Country Flag URL | sourceGeoCountryFlagUrl | String        | 1                   | Country Flag.   |
| Source | Geo Country Name     | sourceGeoCountryName    | String        | 1                   | Country Code.   |
| Source | Geo Descriptor ID    | sourceGeoDescriptorId   | ID            | 1                   | Unique descriptor for the geo field.  |
| Source | Geo Latitude         | sourceGeoLatitude       | Double        | 1                   | See the common set of geographical attributes.  |

| Group  | Label              | Script Alias            | Data Type   | Default Turbo Level | Description  |
|--------|--------------------|-------------------------|-------------|---------------------|--|
| Source | Geo Location Info  | sourceGeoLocationInfo   | String      | 1                   | See the common set of geographical attributes.   |
| Source | Geo Longitude      | sourceGeoLongitude      | Double      | 1                   | See the common set of geographical attributes.   |
| Source | Geo Postal Code    | sourceGeoPostalCode     | String      | 1                   | See the common set of geographical attributes.   |
| Source | Geo Region Code    | sourceGeoRegionCode     | String      | 1                   | See the common set of geographical attributes.   |
| Source | Host Name          | sourceHostName          | String      | 2                   | The name of the source device.   |
| Source | MAC Address        | sourceMacAddress        | MAC address | 2                   | The MAC address associated with the network traffic's source (which may or may not be the MAC address of the host device).         |
| Source | NT Domain          | sourceNtDomain          | String      | 2                   | The Windows NT domain associated with the source device.   |
| Source | Port               | sourcePort              | Integer     | 1                   | The network port associated with the network traffic's source.   |
| Source | Process Name       | sourceProcessName       | String      | 2                   | The name of the process associated with the source of the network traffic.   |
| Source | Service Name       | sourceServiceName       | String      | 2                   | The name of the service associated with the network traffic's source.  |
| Source | Translated Address | sourceTranslatedAddress | IP address  | 1                   | If network address translation is an issue, this is the translated IP address of the device that was the network traffic's source. |
| Source | Translated Port    | sourceTranslatedPort    | Integer     | 1                   | If network address translation is an issue, this is the translated source port associated with the attack.                         |

| Group  | Label                        | Script Alias                    | Data Type | Default Turbo Level | Description   |
|--------|------------------------------|---------------------------------|-----------|---------------------|---|
| Source | Translated Zone              | sourceTranslatedZone            | Zone      | 1                   | If network address translation is an issue, this is the network zone associated with the translated IP address of the device that was the network traffic's source. |
| Source | Translated Zone External ID  | sourceTranslatedZoneExternalID  | String    | 1                   | Returns the external ID for this reference.   |
| Source | Translated Zone ID           | sourceTranslatedZoneID          | String    | 1                   | Returns the ID for the resource in this resource reference.   |
| Source | Translated Zone Name         | sourceTranslatedZoneName        | String    | 1                   | Returns the name from the URI, which is always assumed to be the last field of the URI.   |
| Source | Translated Zone Reference ID | sourceTranslatedZoneReferenceID | ID        | 1                   | Returns the unique descriptor ID for this reference. This is populated only if this reference has been stored and uniquely identified in the database.              |
| Source | Translated Zone Resource     | sourceTranslatedZoneResource    | Resource  | 1                   | Locates the resource described by this reference.   |
| Source | Translated Zone URI          | sourceTranslatedZoneURI         | String    | 1                   | Returns the URI for this reference.   |
| Source | User ID                      | sourceUserId                    | String    | 2                   | The OS- or application-based identifier associated with the user at the network traffic's source.   |
| Source | User Name                    | sourceUserName                  | String    | 2                   | The OS- or application-based name associated with the user at the network traffic's source.   |
| Source | User Privileges              | sourceUserPrivileges            | String    | 2                   | The privileges afforded the user at the network traffic's source.   |

| Group  | Label             | Script Alias          | Data Type | Default Turbo Level | Description  |
|--------|-------------------|-----------------------|-----------|---------------------|--|
| Source | Zone              | sourceZone            | Zone      | 1                   | The network zone where the source device resides.  |
| Source | Zone External ID  | sourceZoneExternalID  | String    | 1                   | Returns the external ID for this reference.  |
| Source | Zone ID           | sourceZoneID          | String    | 1                   | Returns the ID for the resource in this resource reference.  |
| Source | Zone Name         | sourceZoneName        | String    | 1                   | Returns the name from the URI, which is always assumed to be the last field of the URI.  |
| Source | Zone Reference ID | sourceZoneReferenceID | ID        | 1                   | Returns the unique descriptor ID for this reference. This is populated only if this reference has been stored and uniquely identified in the database. |
| Source | Zone Resource     | sourceZoneResource    | Resource  | 1                   | Locates the resource described by this reference.  |
| Source | Zone URI          | sourceZoneURI         | String    | 1                   | Returns the URI for this reference.  |

## Target

| Group  | Label   | Script Alias  | Data Type  | Default Turbo Level | Description  |
|--------|---------|---------------|------------|---------------------|--|
| Target | Address | targetAddress | IP address | 1                   | The IP address of the device hosting the attacker. |

| Group  | Label                | Script Alias            | Data Type     | Default Turbo Level | Description  |
|--------|----------------------|-------------------------|---------------|---------------------|--|
| Target | Asset ID             | targetAssetId           | Resource      | 2                   | The asset that represents the attacked device's host.                    |
| Target | Asset Name           | targetAssetName         | String        | 2                   | See the common set of resource attributes.                               |
| Target | Asset Resource       | targetAssetResource     | Resource      | 2                   | See the common set of resource attributes.                               |
| Target | DNS Domain           | targetDnsDomain         | String        | 2                   | The Domain Name Service domain name associated with the attacked device. |
| Target | FQDN                 | targetFqdn              | String        | 2                   | The fully qualified domain name associated with the attacked device.     |
| Target | Geo                  | targetGeo               | GeoDescriptor | 1                   | The geographical information.  |
| Target | Geo Country Code     | targetGeoCountryCode    | String        | 1                   | Country code.  |
| Target | Geo Country Flag URL | targetGeoCountryFlagUrl | String        | 1                   | Country flag.  |
| Target | Geo Country Name     | targetGeoCountryName    | String        | 1                   | Country name.  |
| Target | Geo Descriptor ID    | targetGeoDescriptorId   | ID            | 1                   | Unique descriptor for the geo field.                                     |
| Target | Geo Latitude         | targetGeoLatitude       | Double        | 1                   | Latitude.  |
| Target | Geo Location Info    | targetGeoLocationInfo   | String        | 1                   | Location information.  |
| Target | Geo Longitude        | targetGeoLongitude      | Double        | 1                   | Longitude.   |
| Target | Geo Postal Code      | targetGeoPostalCode     | String        | 1                   | Postal code.   |
| Target | Geo Region Code      | targetGeoRegionCode     | String        | 1                   | Region code.   |

| Group  | Label                       | Script Alias                   | Data Type   | Default Turbo Level | Description  |
|--------|-----------------------------|--------------------------------|-------------|---------------------|--|
| Target | Host Name                   | targetHostName                 | String      | 2                   | The name of the attacked device.   |
| Target | MAC Address                 | targetMacAddress               | MAC address | 2                   | The MAC address associated with the target of the attack (which may or may not be the MAC address of the host device).                 |
| Target | NT Domain                   | targetNtDomain                 | String      | 2                   | The Windows NT domain associated with the attacked device.   |
| Target | Port                        | targetPort                     | Integer     | 1                   | The network port associated with the target of the attack.   |
| Target | Process Name                | targetProcessName              | String      | 2                   | The name of the process associated with the attack's target.   |
| Target | Service Name                | targetServiceName              | String      | 2                   | The name of service associated with the attack's target.   |
| Target | Translated Address          | targetTranslatedAddress        | IP address  | 1                   | If network address translation is an issue, this is the translated IP address of the attacked device.                                  |
| Target | Translated Port             | targetTranslatedPort           | Integer     | 1                   | If network address translation is an issue, this is the translated port associated with the attack.                                    |
| Target | Translated Zone             | targetTranslatedZone           | Zone        | 1                   | If network address translation is an issue, this is the network zone associated with the translated IP address of the targeted device. |
| Target | Translated Zone External ID | targetTranslatedZoneExternalID | String      | 1                   | Returns the external ID for this reference.  |
| Target | Translated Zone ID          | targetTranslatedZoneID         | String      | 1                   | Returns the ID for the resource in this resource reference.  |



| Group  | Label                        | Script Alias                    | Data Type | Default Turbo Level | Description  |
|--------|------------------------------|---------------------------------|-----------|---------------------|--|
| Target | Translated Zone Name         | targetTranslatedZoneName        | String    | 1                   | Returns the name from the URI, which is always assumed to be the last field of the URI.  |
| Target | Translated Zone Reference ID | targetTranslatedZoneReferenceID | ID        | 1                   | Returns the unique descriptor ID for this reference. This is populated only if this reference has been stored and uniquely identified in the database. |
| Target | Translated Zone Resource     | targetTranslatedZoneResource    | Resource  | 1                   | Locates the resource described by this reference.  |
| Target | Translated Zone URI          | targetTranslatedZoneURI         | String    | 1                   | Returns the URI for this reference.  |
| Target | User ID                      | targetUserId                    | String    | 2                   | The OS- or application-based identifier associated with the attacker, at the target of the attack.   |
| Target | User Name                    | targetUserName                  | String    | 2                   | The OS- or application-based name associated with the attacker, at the target of the attack.   |
| Target | User Privileges              | targetUserPrivileges            | String    | 2                   | The privileges afforded the attacker, at the target of the attack.   |
| Target | Zone                         | targetZone                      | Zone      | 1                   | The network zone in which the attacked device resides.   |
| Target | Zone External ID             | targetZoneExternalID            | String    | 1                   | Returns the external ID for this reference.  |
| Target | Zone ID                      | targetZoneID                    | String    | 1                   | Returns the ID for the resource in this resource reference.  |
| Target | Zone Name                    | targetZoneName                  | String    | 1                   | Returns the name from the URI, which is always assumed to be the last field of the URI.  |

| Group  | Label             | Script Alias          | Data Type | Default Turbo Level | Description  |
|--------|-------------------|-----------------------|-----------|---------------------|--|
| Target | Zone Reference ID | targetZoneReferenceID | ID        | 1                   | Returns the unique descriptor ID for this reference. This is populated only if this reference has been stored and uniquely identified in the database. |
| Target | Zone Resource     | targetZoneResource    | Resource  | 1                   | Locates the resource described by this reference.  |
| Target | Zone URI          | targetZoneURI         | String    | 1                   | Returns the URI for this reference.  |

## Threat

| Group  | Label             | Script Alias     | Data Type | Default Turbo Level | Description   |
|--------|-------------------|------------------|-----------|---------------------|---|
| Threat | Asset Criticality | assetCriticality | Integer   | 2                   | The relative measure of the importance of the targeted device, on a scale of 0 to 10.   |
| Threat | Model Confidence  | modelConfidence  | Integer   | 2                   | The relative measure of ArcSight's confidence in its model of the attacked device, on a scale of 0 to 10.                       |
| Threat | Priority          | priority         | Integer   | 1                   | The relative measure of importance of investigating this event on a scale of 0 to 10. This field incorporates Model Confidence. |
| Threat | Relevance         | relevance        | Integer   | 2                   | The relative measure of likelihood that this event succeeded, on a scale of 0 to 10.  |

| Group  | Label    | Script Alias | Data Type | Default Turbo Level | Description  |
|--------|----------|--------------|-----------|---------------------|--|
| Threat | Severity | severity     | Integer   | 2                   | The relative measure of possible damage to network security represented by the event on a scale of 0 to 10. It may be noted that <b>event severity</b> is supplied by the device; <b>ArcSight severity</b> is supplied by the Smartconnector; and <b>attack severity</b> is supplied by the threat evaluation process. |

### Resource Attributes

| Attribute Suffix | Description  |
|------------------|--|
| External ID      | The user-defined identifier associated with a configuration resource.        |
| ID               | The internal identifier associated with a resource (a UUID).                 |
| Reference ID     | The internal identifier associated with the resource reference (an integer). |
| Type Name        | The type of configuration resource.  |
| URI              | The URI associated with the resource (e.g., /All Users/Administrators/Mlow). |

### Geographical Attributes

| Attribute Suffix | Description  |
|------------------|--|
| Descriptor ID    | The internal ID of the geographical reference.   |
| Country Code     | The identifier for the national-political state in which a device resides.                   |
| Country Flag URL | The URL of an image of the flag of the national-political state in which the device resides. |
| Country Name     | The name of the national-political state where a device resides.                             |
| Latitude         | The latitude of a device (Float).  |
| Location Info    | Other, free-form text information about the device's location.                               |
| Longitude        | The longitude of a device (Float).   |

| Attribute Suffix | Description  |
|------------------|--|
| Postal Code      | The postal code of the device's location, as assigned by the national-political state where it resides.  |
| Region Code      | The identifier of the sub-region of the national-political state where a device resides. The style of the identifier varies with the host country. |

## Audit Events

Audit events are ones generated within ArcSight itself to mark a wide variety of routine actions that can occur manually or automatically, such as adding an event to a case or when a Moving Average data monitor detects a rapidly rising moving average. Audit events have many applications, which can include notifications, task validation, compliance tracking, automated housekeeping, and system administration.

In the table below, use the **Audit Event Category** to locate events. The **Audit Event Description** approximates the Name you see in active channel grids. Additional details, when necessary, appear in the Notes column.

Compare audit events, which report on system activity, with Status Monitor Events, which provide information about a wide variety of system states.

### Audit Event Categories

- Active Channel
- Active List
- Agent Connection
- Agent Exceptions
- Agent Login
- Agent Registration and Configuration
- Authorization
- Configuration Resources
- Dashboard
- Manager Activation
- Manager Database Error Conditions
- Manager External Event Flow Interruption
- Moving Average Data Monitor
- Notification
- Notification Acknowledgement
- Notification Testing
- Partition Archiver
- Partition Manager
- Reconciliation Data Monitor
- Report
- Resource Quota
- Rule Actions

- Rule Activations
- Rule Firings
- Rule Warnings
- Scheduler Execution
- Scheduler Scheduling Tasks
- Scheduler Skip
- Statistical Data Monitor
- Stress
- User Login

### ArcSight Audit Events

| Audit Event Category | Device Event Class ID             | Audit Event Description   |
|----------------------|-----------------------------------|---|
| Active Channel       | <a href="#">activechannel:100</a> | An active channel was opened  |
| Active Channel       | <a href="#">activechannel:101</a> | An empty active channel was opened  |
| Active List          | <a href="#">activelist:101</a>    | An entry was added to an active list  |
| Active List          | <a href="#">activelist:102</a>    | An entry was removed from an active list  |
| Active List          | <a href="#">activelist:103</a>    | An entry was changed in an active list  |
| Agent Connection     | <a href="#">agent:009</a>         | Manager rejected a connection attempt from an agent for reasons other than authentication failure |
| Agent Connection     | <a href="#">agent:30</a>          | Agent started   |
| Agent Connection     | <a href="#">agent:31</a>          | Agent shutdown  |
| Agent Connection     | <a href="#">agent:101</a>         | Agent has just connected to Manager   |
| Agent Connection     | <a href="#">agent:102</a>         | Agent is sending events but no heartbeats   |
| Agent Connection     | <a href="#">agent:103</a>         | Agent is sending neither events nor heartbeats  |
| Agent Connection     | <a href="#">agent:104</a>         | An unknown agent attempted to connect to the Manager  |
| Agent Connection     | <a href="#">agent:105</a>         | An agent presented an incorrect shared secret when authenticating                                 |
| Agent Exceptions     | <a href="#">agent:012</a>         | Agent detected source events from a sensor device containing incorrect time stamps                |
| Agent Exceptions     | <a href="#">agent:013</a>         | Agent noted that a new sensor device is sending events  |
| Agent Exceptions     | <a href="#">agent:014</a>         | Agent could not find a base event referenced in a syslog aggregate event                          |
| Agent Exceptions     | <a href="#">agent:016</a>         | Agent successfully connected to the sensor device's log   |
| Agent Exceptions     | <a href="#">agent:017</a>         | Agent successfully executed a command   |
| Agent Exceptions     | <a href="#">agent:018</a>         | Agent could not execute a command   |
| Agent Exceptions     | <a href="#">agent:019</a>         | Agent is caching events because they could not be immediately transmitted to the Manager          |

| Audit Event Category                 | Device Event Class ID                 | Audit Event Description  |
|--------------------------------------|---------------------------------------|--|
| Agent Exceptions                     | <a href="#">agent:020</a>             | Agent has emptied its cache of events  |
| Agent Exceptions                     | <a href="#">agent:021</a>             | Agent could not communicate with an NT collector sensor  |
| Agent Exceptions                     | <a href="#">agent:023</a>             | Agent could not communicate with a CheckPoint sensor   |
| Agent Exceptions                     | <a href="#">agent:024</a>             | Agent is having difficulty communicating with CheckPoint   |
| Agent Exceptions                     | <a href="#">agent:028</a>             | Agent experienced an unexpected problem  |
| Agent Exceptions                     | <a href="#">agent:029</a>             | Agent was forced to drop its cached data   |
| Agent Exceptions                     | <a href="#">agent:030</a>             | Agent cache filled and part of the cached data was deleted   |
| Agent Login                          | <a href="#">authentication:200</a>    | Successful Agent authentication  |
| Agent Login                          | <a href="#">authentication:201</a>    | Agent authentication failed  |
| Agent Registration and Configuration | <a href="#">agent:007</a>             | Agent successfully registered with Manager   |
| Agent Registration and Configuration | <a href="#">agent:008</a>             | Agent did not successfully register with Manager   |
| Agent Registration and Configuration | <a href="#">agent:029</a>             | Agent configuration was successfully changed   |
| Agent Registration and Configuration | <a href="#">agent:022</a>             | Agent could not process a reconfiguration request  |
| Agent Registration and Configuration | <a href="#">agent:032</a>             | Agent configuration was successfully changed   |
| Agent Registration and Configuration | <a href="#">agent:025</a>             | Agent content was successfully updated   |
| Agent Registration and Configuration | <a href="#">agent:026</a>             | Agent content update failed  |
| Agent Registration and Configuration | <a href="#">agent:010</a>             | Agent upgrade succeeded, This is currently in the context of an installer upgrade.                   |
| Agent Registration and Configuration | <a href="#">agent:011</a>             | Agent upgrade failed. This event is not currently being generated.                                   |
| Authorization                        | <a href="#">authorization:100</a>     | Manager refused to authorize client  |
| Configuration Resources              | <a href="#">resource:100</a>          | Deleted a configuration resource   |
| Configuration Resources              | <a href="#">resource:101</a>          | Updated a configuration resource   |
| Configuration Resources              | <a href="#">resource:102</a>          | Added a new configuration resource   |
| Configuration Resources              | <a href="#">resourcereference:100</a> | Could not locate a configuration resource. Through the supplied universal resource identifier (URI). |
| Dashboard                            | <a href="#">dashboard:100</a>         | Dashboard has opened   |

| Audit Event Category                     | Device Event Class ID            | Audit Event Description   |
|--|----------------------------------|---|
| Manager Activation                       | <a href="#">manager:100</a>      | Manager has started   |
| Manager Activation                       | <a href="#">manager:101</a>      | A clean Manager shutdown has been requested   |
| Manager Database Error Conditions        | <a href="#">database:100</a>     | Database tablespace is low and will be deactivated  |
| Manager Database Error Conditions        | <a href="#">database:101</a>     | Database has generated a fatal error and will be deactivated  |
| Manager Database Error Conditions        | <a href="#">database:102</a>     | Database has been reactivated   |
| Manager Database Error Conditions        | <a href="#">database:103</a>     | Database has more tablespace available after detecting a low tablespace condition                   |
| Manager External Event Flow Interruption | <a href="#">manager:200</a>      | Manager has stopped the event flow  |
| Manager External Event Flow Interruption | <a href="#">manager:201</a>      | Manager has allowed the event flow to resume  |
| Moving Average Data Monitor              | <a href="#">datamonitor:102</a>  | Moving Average data monitor detected a rapidly falling moving average                               |
| Moving Average Data Monitor              | <a href="#">datamonitor:103</a>  | Moving Average data monitor detected a rapidly rising moving average                                |
| Moving Average Data Monitor              | <a href="#">datamonitor:104</a>  | Moving Average data monitor reporting the current moving average                                    |
| Notification                             | <a href="#">notification:100</a> | Notification has been disabled  |
| Notification                             | <a href="#">notification:101</a> | Notification has been disabled because the queue of notifications to be sent is too large           |
| Notification                             | <a href="#">notification:102</a> | Notification has been enabled   |
| Notification                             | <a href="#">notification:103</a> | Notification has been enabled because the queue of notifications is back under control              |
| Notification                             | <a href="#">notification:104</a> | A particular notification destination has been disabled   |
| Notification                             | <a href="#">notification:105</a> | A particular notification destination has been disabled because too much traffic was directed at it |
| Notification                             | <a href="#">notification:106</a> | A particular notification destination has been enabled  |
| Notification                             | <a href="#">notification:107</a> | A notification expired without being acknowledged   |
| Notification                             | <a href="#">notification:108</a> | A functioning destination could not be located for this notification                                |
| Notification                             | <a href="#">notification:109</a> | Old notification has been purged  |
| Notification Acknowledgement             | <a href="#">notification:300</a> | This notification has been acknowledged   |
| Notification Testing                     | <a href="#">notification:200</a> | Sent a test notification to this destination group  |

| Audit Event Category        | Device Event Class ID                 | Audit Event Description   |
|-----------------------------|---------------------------------------|---|
| Partition Archiver          | <a href="#">partitionarchiver:100</a> | The partition was successfully archived                                 |
| Partition Archiver          | <a href="#">partitionarchiver:200</a> | There was a problem while archiving the partition                       |
| Partition Archiver          | <a href="#">partitionarchiver:300</a> | Partition archiving is disabled   |
| Partition Archiver          | <a href="#">partitionarchiver:400</a> | Partition archiving did not complete in the allotted time               |
| Partition Archiver          | <a href="#">partitionarchiver:500</a> | Partition archiving failed  |
| Partition Archiver          | <a href="#">partitionarchiver:600</a> | There was an unexpected error while archiving partitions                |
| Partition Manager           | <a href="#">partitionmanager:100</a>  | Partitions have been successfully rotated                               |
| Partition Manager           | <a href="#">partitionmanager:200</a>  | There was a problem rotating partitions                                 |
| Partition Manager           | <a href="#">partitionmanager:300</a>  | The partition manager has been disabled                                 |
| Partition Manager           | <a href="#">partitionmanager:500</a>  | Partitions could not be rotated   |
| Partition Manager           | <a href="#">partitionmanager:600</a>  | There was an unexpected error while rotating partitions                 |
| Reconciliation Data Monitor | <a href="#">datamonitor:300</a>       | Correlation data monitor reporting a correlated or non-correlated event |
| Report                      | <a href="#">report:100</a>            | Generated a new archived-report configuration resource                  |
| Report                      | <a href="#">report:101</a>            | Failed to generate a new archived-report configuration resource         |
| Report                      | <a href="#">report:102</a>            | Generated a new delta archived-report configuration resource            |
| Resource Quota              | <a href="#">quota:100</a>             | Resource usage has fallen below the fixed-quota level                   |
| Resource Quota              | <a href="#">quota:101</a>             | Resource usage has exceeded the fixed-quota level                       |
| Resource Quota              | <a href="#">quota:102</a>             | Asset autocreation has exceeded a fixed quota                           |
| Resource Quota              | <a href="#">quota:103</a>             | Asset autocreation is proceeding too rapidly                            |
| Rule Actions                | <a href="#">rule:301</a>              | Set Severity action. This event has been deprecated.                    |
| Rule Actions                | <a href="#">rule:302</a>              | Set Event Attribute action  |
| Rule Actions                | <a href="#">rule:303</a>              | Send to Notifier action   |
| Rule Actions                | <a href="#">rule:304</a>              | Execute Command action  |
| Rule Actions                | <a href="#">rule:305</a>              | Export... action  |
| Rule Actions                | <a href="#">rule:306</a>              | Create New Case action  |
| Rule Actions                | <a href="#">rule:307</a>              | Add to Case action  |



| Audit Event Category       | Device Event Class ID         | Audit Event Description  |
|----------------------------|-------------------------------|--|
| Rule Actions               | <a href="#">rule:308</a>      | Create New Case action failed  |
| Rule Actions               | <a href="#">rule:309</a>      | Add to Case action failed  |
| Rule Actions               | <a href="#">rule:310</a>      | Add to Active List action  |
| Rule Actions               | <a href="#">rule:311</a>      | Move between Active Lists action. This event has been deprecated.                                |
| Rule Actions               | <a href="#">rule:312</a>      | Remove from Active List action   |
| Rule Activations           | <a href="#">rule:700</a>      | Rule has been deactivated  |
| Rule Activations           | <a href="#">rule:701</a>      | Rule has been deactivated because it is unsafe. There was excessive recursion or event matching. |
| Rule Activations           | <a href="#">rule:702</a>      | Rule has been activated  |
| Rule Firings               | <a href="#">rule:101</a>      | Rule fired OnEveryEvent  |
| Rule Firings               | <a href="#">rule:102</a>      | Rule fired OnFirstEvent  |
| Rule Firings               | <a href="#">rule:103</a>      | Rule fired OnSubsequentEvents  |
| Rule Firings               | <a href="#">rule:104</a>      | Rule fired OnEveryThreshold  |
| Rule Firings               | <a href="#">rule:105</a>      | Rule fired OnFirstThreshold  |
| Rule Firings               | <a href="#">rule:106</a>      | Rule fired OnSubsequentThresholds  |
| Rule Firings               | <a href="#">rule:107</a>      | Rule fired OnTimeUnitExpiration  |
| Rule Warnings              | <a href="#">rule:501</a>      | Rule is firing on events generated by itself   |
| Scheduler Execution        | <a href="#">scheduler:200</a> | A task has been executed   |
| Scheduler Execution        | <a href="#">scheduler:201</a> | A task failed to execute   |
| Scheduler Scheduling Tasks | <a href="#">scheduler:300</a> | A new task has been scheduled  |
| Scheduler Scheduling Tasks | <a href="#">scheduler:301</a> | A new task could not be scheduled  |
| Scheduler Scheduling Tasks | <a href="#">scheduler:302</a> | Enabled a task   |
| Scheduler Scheduling Tasks | <a href="#">scheduler:303</a> | Could not enable a task  |
| Scheduler Scheduling Tasks | <a href="#">scheduler:304</a> | Deleted a task   |
| Scheduler Scheduling Tasks | <a href="#">scheduler:305</a> | Failed to delete a task  |
| Scheduler Scheduling Tasks | <a href="#">scheduler:306</a> | Disable a task   |
| Scheduler Scheduling Tasks | <a href="#">scheduler:307</a> | Could not disable a task   |

| Audit Event Category     | Device Event Class ID           | Audit Event Description   |
|--------------------------|---------------------------------|---|
| Scheduler Skip           | <code>scheduler:100</code>      | The task scheduler skipped a scheduled task execution because the scheduler was not allowed to run                |
| Scheduler Skip           | <code>scheduler:101</code>      | The task scheduler skipped a scheduled task invocation because the last invocation of the task is still executing |
| Statistical Data Monitor | <code>datamonitor:200</code>    | Statistical Data Monitor reporting a change in status   |
| Stress                   | <code>test:100</code>           | A stress test event. This event is generated only by ArcSight Quality Assurance.                                  |
| User Login               | <code>authentication:100</code> | Successful client login   |
| User Login               | <code>authentication:101</code> | Failed client login   |
| User Login               | <code>authentication:102</code> | Client logout   |
| User Login               | <code>authentication:103</code> | Client timed out due to inactivity  |
| User Login               | <code>authentication:104</code> | Too many client login failures occurred within a time period  |

## Status Monitor Events

ArcSight status monitor events can reveal and isolate many different quantity and time-unit issues that bear directly on performance and capacity. There are many possible applications of this system-state data, but those applications must always be interpreted within the context of your particular hardware, software, and network environment, and the deployment choices made for ArcSight and its SmartConnectors.

Compare status monitoring events, which provide information about a wide variety of system states, to Audit Events, which report on system activity.

- Active Channel Statistics
- Active List Statistics
- Asset Statistics
- Data Monitor Statistics
- Event Broker Statistics
- Filter Engine Statistics
- Main Flow Statistics
- Notification Statistics
- Pattern Discovery Statistics
- Report Statistics
- Resource Framework Statistics
- Rules Engine Statistics
- Session Management Statistics
- Side Table Statistics
- SmartConnector Flow Statistics

## Active Channel Statistics

Active channel statistics, specifically any changes that occur in the counts they report, can indicate performance issues and the use of processing cycles. These events summarize:

- The number of events changed across all open Active Channels per second
- The number of events inserted into Active Channels per second
- The number of currently open Active Channels

| Status Monitor Event Category              | Device Event Class ID | Audit Event Description  |
|--|-----------------------|--|
| /Monitor/ActiveChannels/Open               | monitor:100           | Open active channel count.<br><br>Provides count and current value.                                    |
| /Monitor/ActiveChannels/Events /Insertions | monitor:174           | Active channel event insertions per second.<br><br>Provides count per second since last monitor event. |
| /Monitor/ActiveChannels/Events /Changes    | monitor:175           | Active channel event changes per second.<br><br>Provides count per second since last monitor event.    |

## Active List Statistics

Active list statistics monitor the resources being used by active lists. Active lists entries use some memory and database resources, and use CPU resources when they are referenced by other parts of the system (e.g., rules, reports, and filters). While changes to these temporary lists are not persisted, they do represent some memory overhead. Note that when active lists are used by replay-with-rules, this also creates temporary lists.

| Status Monitor Event Category           | Device Event Class ID | Audit Event Description  |
|---|-----------------------|--|
| /Monitor/ActiveLists/ListCount          | monitor:114           | Open active list count.<br><br>Provides count, current value.      |
| /Monitor/ActiveLists/EntryCount         | monitor:115           | Active list entry count.<br><br>Provides count, current value.     |
| /Monitor/ActiveLists/EntryCapacity      | monitor:116           | Active list entry capacity.<br><br>Provides count, current value.  |
| /Monitor/ActiveLists/EntryPercentUsed   | monitor:117           | Active list entry usage.<br><br>Provides percent, current value.   |
| /Monitor/ActiveLists/TemporaryListCount | monitor:118           | Temporary Active list count.<br><br>Provides count, current value. |

| Status Monitor Event Category                | Device Event Class ID | Audit Event Description  |
|--|-----------------------|--|
| /Monitor/ActiveLists/TemporaryEntryCount     | monitor:119           | Temporary Active list entry count.<br><br>Provides count, current value.                   |
| /Monitor/ActiveLists/TemporaryCapacity       | monitor:120           | Temporary Active list capacity.<br><br>Provides count, current value.                      |
| /Monitor/ActiveLists/TemporaryPercentageUsed | monitor:121           | Temporary Active list usage.<br><br>Provides percent, current value.                       |
| /Monitor/ActiveLists/QueriesPerSecond        | monitor:122           | Active list queries per second.<br><br>Provides count of queries per second since startup. |
| /Monitor/ActiveLists/ChangesPerSecond        | monitor:123           | Active list changes per second.<br><br>Count per second since startup.                     |

### Asset Statistics

Asset statistics offer insight into performance areas that affect assets in the system and can help resolve source, destination, agent, and device asset issues for incoming events. These events summarize:

- **Asset resolutions per second** is the average number of end-points in events, that are resolved to assets in a second.
- **Asset resolutions average time** is the average time in milliseconds taken to resolve an end-point in an event to an asset.
- **Asset scanner events per second** is the number of scanner events processed in a second.
- **Asset scanner events average time** is the average time in milliseconds taken to process a scanner event.

| Status Monitor Event Category          | Device Event Class ID | Audit Event Description  |
|--|-----------------------|--|
| /Monitor/Asset/TotalCount              | monitor:200           | Asset total count.<br><br>Provides count, current value.   |
| /Monitor/Asset/Scanner/EventsPerSecond | monitor:201           | Scanner events processed per second.<br><br>Provides count per second since last monitor event.                                  |
| /Monitor/Asset/ResolutionsPerSecond    | monitor:202           | Asset resolutions per second.<br><br>Provides count per second for asset resolutions since last monitor event.                   |
| /Monitor/Asset/Scanner/AverageTime     | monitor:203           | Scanner event average processing time.<br><br>Provides count per second for scanner event average processing time since startup. |

| Status Monitor Event Category                     | Device Event Class ID | Audit Event Description   |
|---|-----------------------|---|
| /Monitor/Asset/ResolutionsAverageTime             | monitor:204           | Asset resolution average time.<br><br>Provides average time in milliseconds for asset resolution since startup.                         |
| /Monitor/Asset/ResolutionsAverageTime/Source      | monitor:205           | Asset source resolution average time.<br><br>Provides average time in milliseconds for asset source resolution since startup.           |
| /Monitor/Asset/ResolutionsAverageTime/Destination | monitor:206           | Asset destination resolution average time.<br><br>Provides average time in milliseconds for asset destination resolution since startup. |
| /Monitor/Asset/Size                               | monitor:240           | Transitive Closure Size.<br><br>Provides count per second and current value for transitive closure size.                                |

### Data Monitor Statistics

The data monitor statistics indicate how intensively the data monitors are working, which in turn can indicate situations such as filters needing adjustment or data monitors needing restructuring. These events summarize:

- **Active probes** is the number of currently enabled data monitors.
- **Evaluations per second** is the number of events times the number of enabled data monitors per second.

| Status Monitor Event Category              | Device Event Class ID | Audit Event Description   |
|--|-----------------------|---|
| /Monitor/DataMonitors/ActiveProbes         | monitor:101           | Active data monitor probe count.<br><br>Provides count, current value.                          |
| /Monitor/DataMonitors/EvaluationsPerSecond | monitor:124           | Data monitor evaluations per second.<br><br>Provides count per second since last monitor event. |

### Event Broker Statistics

These statistics monitor reading events from, and writing events to, the database. As such, they are database health indicators. These events summarize:

- **Event count** is the number of events inserted into the database since the last monitor event.
- **Insert time** is the average time taken to insert each event into the database, in microseconds.

- **Retrieval time** is the average time taken to retrieve each event from the database in microseconds.

| Status Monitor Event Category           | Device Event Class ID | Audit Event Description  |
|---|-----------------------|--|
| /Monitor/EventBroker/InsertTime         | monitor:102           | Events insertion time per event<br><br>Provides count in microseconds for insertion time per event since last monitor event. |
| /Monitor/EventBroker/InsertedEventCount | monitor:103           | Events processed count.<br><br>Provides count since last monitor event.  |
| /Monitor/EventBroker/RetrievalTime      | monitor:140           | Events retrieval time per event.<br><br>Provides count in microseconds per count, since last monitor event.                  |

### Filter Engine Statistics

The count of in-memory filter evaluations can serve as a broad indicator of filter performance.

| Status Monitor Event Category    | Device Event Class ID | Audit Event Description  |
|----------------------------------|-----------------------|--------------------------|
| /Monitor/Filters/EvaluationCount | monitor:161           | Filter evaluation count. |

### Main Flow Statistics

These events report statistically on the overall throughput of the ArcSight Manager, for both incoming and internal events. This flow is the sequence of processing steps applied to each event and is a broad indicator or benchmark of system traffic. These events summarize:

- **Count** describes the number of events that have passed through the flow since the manager started.
- **Rate** describes the current event rate in events per second.

| Status Monitor Event Category | Device Event Class ID | Audit Event Description  |
|-------------------------------|-----------------------|--|
| /Monitor/MainFlow/EPS         | monitor:230           | Main flow event rate.<br><br>Provides count per second since last monitor event. |
| /Monitor/MainFlow/Events      | monitor:231           | Main flow event count.<br><br>Provides count since startup.                      |

### Notification Statistics

This group reports on notification activity, which can be of diagnostic value in detecting unusually high notifications activity.

- **New count** describes the number of new notifications since the last monitor event.

- **Escalated count** describes the number of notifications that were escalated since the last monitor event.

| Status Monitor Event Category   | Device Event Class ID       | Audit Event Description   |
|---------------------------------|-----------------------------|---|
| /Monitor/Notification/New       | <a href="#">monitor:180</a> | New notification count.<br>Provides count since last monitor event.       |
| /Monitor/Notification/Escalated | <a href="#">monitor:181</a> | Escalated notification count.<br>Provides count since last monitor event. |

### Pattern Discovery Statistics

These events provide statistics for recent or pending pattern discovery runs. Because pattern discovery is database-intensive, these statistics can indicate or help diagnose database performance issues.

| Status Monitor Event Category | Device Event Class ID       | Audit Event Description  |
|-------------------------------|-----------------------------|--|
| /Monitor/Patterns/RunCount    | <a href="#">monitor:190</a> | Pattern discoveries run count.<br>Provides count since last monitor event. |
| /Monitor/Patterns/RunsQueued  | <a href="#">monitor:191</a> | Pattern discoveries queued count.<br>Provides count current value.         |

### Report Statistics

These events provide statistics about the current number of reports querying the database or being rendered. Because reports are database-intensive, these statistics can indicate or help diagnose database performance issues.

| Status Monitor Event Category      | Device Event Class ID       | Audit Event Description  |
|------------------------------------|-----------------------------|--|
| /Monitor/Reports/Running           | <a href="#">monitor:130</a> | Reports running count.<br>Provides count, current value.           |
| /Monitor/Reports/RunningQueryingDB | <a href="#">monitor:131</a> | Reports querying database count.<br>Provides count, current value. |
| /Monitor/Reports/RunningRendering  | <a href="#">monitor:132</a> | Reports rendering count.<br>Provides count, current value.         |

### Resource Framework Statistics

Resource-framework events report on the database activity connected with updates (reads, writes, and deletions) to system resources such as rules, assets, and filters, since the last

monitor event. This data can be valuable in tracking or diagnosing performance-related issues such as automatic asset maintenance, the threat-level formula, or rule-driven usage.

| Status Monitor Event Category     | Device Event Class ID       | Audit Event Description   |
|-----------------------------------|-----------------------------|---|
| /Monitor/Resource/Activity/Insert | <a href="#">monitor:171</a> | Resources inserted per second.<br><br>Provides count per second since last monitor event. |
| /Monitor/Resource/Activity/Update | <a href="#">monitor:172</a> | Resources updated per second.<br><br>Provides count per second since last monitor event.  |
| /Monitor/Resource/Activity/Delete | <a href="#">monitor:173</a> | Resources deleted per second.<br><br>Provides count per second since last monitor event.  |

### Rules Engine Statistics

The statistics related to the ArcSight Manager's rules engine can help reveal performance issues in several areas. Please remember that information about rules activity always needs to be considered in the full content of the Manager's operations. For example, a busy Moving Average data monitor, if used inefficiently, can affect several of these statistics; a poorly written rule can inadvertently drive up the rate of actions executed.

These statistics have the following performance implications

- Count of events inserted into the rule engine: CPU.
- Rate of event insertion into the rule engine: CPU.
- Count of correlated events generated by the rule engine: CPU.
- Rate of correlated event generation by the rule engine: CPU.
- Count of partial matches in the rule engine: memory.
- Count of events that are still present in rule engine's working memory: memory.
- Count of groupBy cells that are being used by the rule engine: memory.
- Count of rules currently active in the rule engine: comparative value only.
- Rate of actions being executed by the rule engine: CPU.

| Status Monitor Event Category     | Device Event Class ID       | Audit Event Description   |
|-----------------------------------|-----------------------------|---|
| /Monitor/Rules/InsertedEventCount | <a href="#">monitor:151</a> | Rules total event count.<br><br>Provides count since last monitor event.                      |
| /Monitor/Rules/InsertedEventRate  | <a href="#">monitor:152</a> | Rules inserted events per second.<br><br>Provides count per second since last monitor event.  |
| /Monitor/Rules/GeneratedEventRate | <a href="#">monitor:153</a> | Rules generated events per second.<br><br>Provides count per second since last monitor event. |



| Status Monitor Event Category           | Device Event Class ID | Audit Event Description  |
|---|-----------------------|--|
| /Monitor/Rules/PartialMatchCount        | monitor:154           | Rules partial match count.<br>Provides count, current value.               |
| /Monitor/Rules/EventsInRuleEngineMemory | monitor:155           | Rules in-memory event count.<br>Provides count, current value.             |
| /Monitor/Rules/GroupByCellsSize         | monitor:156           | Rules group by cells size.<br>Provides count, current value.               |
| /Monitor/Rules/ActiveRulesCount         | monitor:157           | Active rules count.<br>Provides count, current value.                      |
| /Monitor/Rules/ActionsTakenRate         | monitor:158           | Rules actions rate.<br>Provides count per second since last monitor event. |
| /Monitor/Rules/GeneratedEventCount      | monitor:159           | Rules generated event count.<br>Provides count since last monitor event.   |

### Session Management Statistics

This statistic tracks the current number of active user sessions.

| Status Monitor Event Category  | Device Event Class ID | Audit Event Description                                    |
|--------------------------------|-----------------------|--|
| /Monitor/Sessions/Active/Total | monitor:160           | Active session count.<br>Provides count and current value. |

### Side Table Statistics

Side tables are ones held in-memory and in the database to retain common and relatively static information, similar to a cache. The purpose is to improve access times for inserts and queries. Side tables store event data that includes: geographical information, categorization information, agent information, device information and labels for custom strings and numbers.

- **Size** identifies how many entries are presently in the cache.
- **Insert** identifies the number of inserts in the past two hours.
- **Cache** misses identifies how many failed attempts to find entries occurred in the past two hours.

- **Cache hit rate** identifies how many successful attempts to find entries occurred in the past two hours.

| Status Monitor Event Category           | Device Event Class ID       | Audit Event Description   |
|---|-----------------------------|---|
| /Monitor/SideTable/GeoInfo/HitRate      | <a href="#">monitor:210</a> | Geo info sidetable cache hit rate.<br><br>Provides a percentage over a moving time frame. |
| /Monitor/SideTable/GeoInfo/Inserts      | <a href="#">monitor:211</a> | Geo info sidetable inserts.<br><br>Provides count over a moving timeframe.                |
| /Monitor/SideTable/GeoInfo/CacheMisses  | <a href="#">monitor:212</a> | Geo info sidetable cache misses.<br><br>Provides count over a moving timeframe.           |
| /Monitor/SideTable/GeoInfo/Size         | <a href="#">monitor:213</a> | Geo info sidetable size.<br><br>Provides count, current value.                            |
| /Monitor/SideTable/Category/HitRate     | <a href="#">monitor:214</a> | Category sidetable cache hit rate.<br><br>Provides a percentage over a moving timeframe.  |
| /Monitor/SideTable/Category/Inserts     | <a href="#">monitor:215</a> | Category sidetable inserts.<br><br>Provides count over a moving timeframe.                |
| /Monitor/SideTable/Category/CacheMisses | <a href="#">monitor:216</a> | Category sidetable cache misses.<br><br>Provides count over a moving timeframe.           |
| /Monitor/SideTable/Category/Size        | <a href="#">monitor:217</a> | Category sidetable size.<br><br>Provides count, current value.                            |
| /Monitor/SideTable/Agent/HitRate        | <a href="#">monitor:218</a> | Agent sidetable cache hit rate.<br><br>Provides a percentage over a moving timeframe.     |
| /Monitor/SideTable/Agent/Inserts        | <a href="#">monitor:219</a> | Agent sidetable inserts.<br><br>Provides count over a moving timeframe.                   |
| /Monitor/SideTable/Agent/CacheMisses    | <a href="#">monitor:220</a> | Agent sidetable cache misses.<br><br>Provides count over a moving timeframe.              |
| /Monitor/SideTable/Agent/Size           | <a href="#">monitor:221</a> | Agent sidetable size.<br><br>Provides count, current value.                               |
| /Monitor/SideTable/Device/HitRate       | <a href="#">monitor:222</a> | Device sidetable cache hit rate.<br><br>Provides a percentage over a moving timeframe.    |
| /Monitor/SideTable/Device/Inserts       | <a href="#">monitor:223</a> | Device sidetable inserts.<br><br>Provides count over a moving timeframe.                  |

| Status Monitor Event Category         | Device Event Class ID | Audit Event Description  |
|---------------------------------------|-----------------------|--|
| /Monitor/SideTable/Device/CacheMisses | monitor:224           | Device sidetable cache misses.<br>Provides count over a moving timeframe.          |
| /Monitor/SideTable/Device/Size        | monitor:225           | Device sidetable size.<br>Provides count, current value.                           |
| /Monitor/SideTable/Labels/HitRate     | monitor:226           | Labels sidetable cache hit rate.<br>Provides a percentage over a moving timeframe. |
| /Monitor/SideTable/Labels/Inserts     | monitor:227           | Labels sidetable inserts.<br>Provides count over a moving timeframe.               |
| /Monitor/SideTable/Labels/CacheMisses | monitor:228           | Labels sidetable cache misses.<br>Provides count over a moving timeframe.          |
| /Monitor/SideTable/Labels/Size        | monitor:229           | Labels sidetable size.<br>Provides count, current value.                           |

### SmartConnector Flow Statistics

SmartConnector flow statistics record the event rates that occur at different stages of agent processing. "Sum of" statistics are sums of all values reported by all agents connected to the ArcSight Manager. All values are statistics over the past 1-minute range. These events summarize:

- **Received event rate** is the rate at which agents receive events from devices.
- Post filter event rate is the rate of events that passed the filter (e.g., were not filtered out).
- **Post aggregation event rate** is the rate of event aggregation.
- **Agent-to-manager event rate and count** describe how many events were actually sent to the Manager.
- **Cache size** describes the estimated size of the on-disk agent event cache.

| Status Monitor Event Category    | Device Event Class ID | Audit Event Description  |
|----------------------------------|-----------------------|--|
| /Monitor/Agents/Events/ToManager | monitor:104           | Agent output event count, since startup.<br>Provides count.  |
| /Monitor/Agents/EPS/ToManager    | monitor:109           | Agent output event rate.<br>Provides count per second and agent-to-manager since last monitor event.             |
| /Monitor/Agents/EPS/Received     | monitor:110           | Agent input event rate.<br>Provides count per second for the agent received event rate since last monitor event. |

| Status Monitor Event Category             | Device Event Class ID       | Audit Event Description   |
|---|-----------------------------|---|
| /Monitor/Agents/EPS/PostFilter            | <a href="#">monitor:111</a> | Agent filtered event rate.<br><br>Provides count per second for the agent post-filter event rate since last monitor event.                            |
| /Monitor/Agents/EPS/PostAggregation       | <a href="#">monitor:112</a> | Agent aggregated event rate.<br><br>Provides count per second for the agent post-aggregation event rate since last monitor event.                     |
| /Monitor/Agents/CacheSize                 | <a href="#">monitor:113</a> | Estimated agent cache size, current value.<br><br>Provides count.   |
| /Monitor/Agents/Total/Events/To Manager   | <a href="#">monitor:141</a> | Sum of agent output event counts.<br><br>Provides count-per-second sum of agent-to-manager event counts since startup.                                |
| /Monitor/Agents/Total/EPS/ToManager       | <a href="#">monitor:146</a> | Sum of agent-to-manager output event rates.<br><br>Provides counted per-second since last monitor event.  |
| /Monitor/Agents/Total/EPS/Received        | <a href="#">monitor:147</a> | Sum of agent input event rates.<br><br>Provides count per second for the sum of agent received event rates since last monitor event.                  |
| /Monitor/Agents/Total/EPS/PostFilter      | <a href="#">monitor:148</a> | Sum of agent filtered event rates.<br><br>Provides count per second for the sum of agent post-filter event rates since last monitor event.            |
| /Monitor/Agents/Total/EPS/PostAggregation | <a href="#">monitor:149</a> | Sum of agent aggregated event rates.<br><br>Provides count per second for the sum of agent post-aggregation event rates since the last monitor event. |
| /Monitor/Agents/Total/CacheSize           | <a href="#">monitor:150</a> | Sum of estimated agent cache sizes.<br><br>Provides count as a sum of the estimated agent cache sizes current value.                                  |

## Chapter 5

# Using Cases

---

ArcSight cases provide organized, workflow-style tracking and management of interesting events or situations.

The ArcSight Web interface enables you to create, manage, or customize cases.

Cases have a large number of fields to cover a wide range of event analysis and investigation possibilities. (See [“Creating Cases” on page 95](#).)



You can add an **Export** button to the Cases display to export selected cases. Add the line `ui.export.enabled=true` to the `webserver.properties` file and restart ArcSight Web.

[“Managing Cases” on page 93](#)

[“Creating Cases” on page 95](#)

## Managing Cases

The cases display shows cases that are already created in the Cases tree. From the main panel, you can select, view, and customize existing cases, and create new ones.

### To view an existing case

- 1 Navigate to and select the case in the Cases resource tree on the left.
  - ◆ Click the group folders in the tree to open or close them.
  - ◆ Click a folder to see a list of its cases in the pane to the right.
  - ◆ Click the arrow icon in the upper-right corner of the resource pane to hide it or show it.
- 2 The Cases content pane shows individual listings. Click an individual case to see its fields (see [“Creating Cases” on page 95](#)).

### To edit an individual case

- 1 Click **Lock this case**.
- 2 Make your changes and click **Submit**.
- 3 Unlock a case after you finish editing.

### To remove a case

- 1 Select the check box for the case you want to remove and click **Remove**.

If you want to keep the case but not allow others to edit it, you can Lock (hold for editing) or Unlock (release for others to edit) buttons.

- 2 Click **Refresh** to update the display.

#### To create a new case

Click **New Case** to go to the Create a New Case display. For details about how to create a case, see [“Creating Cases” on page 95](#).

#### To customize a case

Click **Customize** to select, deselect, and arrange the columns of the case list.

## Default Case Management Columns

| Attribute                    | Description  |
|------------------------------|--|
| Name                         | The name assigned to the case. Using descriptive names is important.   |
| Locked                       | Whether the case is free to be edited by others. If Locked, it cannot.   |
| Security Classification Code | The letter codes that identify the nature of the security issues the case represents. See <a href="#">“Security Classification Default Letter Codes” on page 94</a> below. |
| Ticket Type                  | The source of the case or its means of tracking.   |
| Stage                        | The current collaboration or workflow stage assigned to the case.  |
| Frequency                    | The numerical range of events that occur in regard to a case.  |
| Created By                   | The ArcSight user ID of the person who created the case.   |

## Security Classification Default Letter Codes

| Classification Category | Letter Codes                |
|-------------------------|-----------------------------|
| Attack Mechanism        | I = Informational           |
|                         | O = Operational             |
|                         | P = Physical                |
|                         | U = Unknown                 |
| Attack Agent            | C = Collaborative           |
|                         | I = Insider                 |
|                         | O = Outsider                |
|                         | U = Unknown                 |
| Vulnerability           | D = Design                  |
|                         | E = Operational Environment |
|                         | O = Operational             |
|                         | U = Unknown                 |

| Classification Category | Letter Codes        |
|-------------------------|---------------------|
| Sensitivity             | C = Confidential    |
|                         | S = Secret          |
|                         | T = Top Secret      |
|                         | U = Unclassified    |
| Associated Impact       | A = Availability    |
|                         | C = Confidentiality |
|                         | I = Integrity       |
|                         | U = Unknown         |
| Action                  | B = Block/Shutdown  |
|                         | M = Monitoring      |
|                         | O = Other           |

## Creating Cases

To create a case, choose the Initial attributes tab first. Fill in the required and other appropriate fields, tab by tab, then click **Submit** at the bottom of the display. Overall, the tabs represent:

- **Initial** - Basic case information: case ticket attributes, description and security classification.
- **Follow Up** - Description of actions taken, planned, or recommended.
- **Final** - Ticket resolution and reporting including attack mechanism, attack agent, incident information, and vulnerability information.
- **Events** - List of events included in case.
- **Notes** - Miscellaneous information applicable to a case.

Display ID numbers are assigned automatically when you save the case.

## Initial Tab

The fields on this tab provide basic case information.

| Field  | Description  |
|--------|--|
| Case   | Name<br>Required field specifying name of case.                              |
|        | Display ID<br>An automatically assigned unique number.                       |
| Ticket | Ticket Type<br>Drop-down list includes Internal, Client, and Incident types. |

| Field                   | Description  |
|-------------------------|--|
| Stage                   | Indicate workflow stage of ticket; selections include Queued, Initial, Follow-up, Final, and Closed.   |
| Frequency               | Indicates how often reported issue occurs. Values assigned are 0 (never or once), 1 (less than 10 times), 2 (10 to 15 times), 3 (15 times), 4 (more than 15).  |
| Operational Impact      | Impact of reported issue. Values assigned are 0 (no impact), 1 (no immediate impact), 2 (low-priority impact), 3 (high-priority impact), 4 (immediate impact). |
| Security Classification | Values assigned are 1 (Unclassified), 2 (Confidential), 3 (Secret), 4 (Top Secret).  |
| Consequence Severity    | Values assigned are 0 (None), 1 (Insignificant), 2 (Marginal), 3 (Critical), 4 (Catastrophic).   |
| Reporting Level         | This is a calculated number, based on Ticket info values entered.  |
| Incident Information    |  |
| Detection Time          | This field is auto-populated.  |
| Estimated Start Time    | This field is auto-populated.  |
| Estimated Restore Time  | This field is auto-populated.  |
| External ID             | This field is auto-populated.  |
| Alias                   | Another name by which the incident is referenced in the system.  |
| Description             | A text description of the incident.  |
| Assign                  |  |
| Owner                   | Users designated as owners of the case.  |
| Notification Groups     | Pre-defined groups that should be notified when the case is created or updated.  |
| Description             |  |
| Affected Services       | This text field can contain up to 4,000 characters.  |
| Affected Elements       | This text field can contain up to 4,000 characters.  |
| Estimated Impact        | This text field can contain up to 4,000 characters.  |
| Affected Sites          | This text field can contain up to 4,000 characters.  |
| Security Classification |  |



| Field                        | Description   |
|------------------------------|---|
| Attack Mechanism             | I = Informational<br>O = Operational<br>P = Physical<br>U = Unknown     |
| Attack Agent                 | C = Collaborative<br>I = Insider<br>O = Outsider<br>U = Unknown         |
| Incident Source 1            | This field is auto-populated.   |
| Incident Source 2            | This field is auto-populated.   |
| Vulnerability                | D = Design<br>E = Operational Environment<br>U = Unknown                |
| Sensitivity                  | C = Confidential<br>S = Secret<br>T = Top Secret<br>U = Unclassified    |
| Associated Impact            | A = Availability<br>C = Confidentiality<br>I = Integrity<br>U = Unknown |
| Action                       | B = Block/Shutdown<br>M = Monitoring<br>O = Other                       |
| Security Classification Code |   |
| Security Classification Code | This field is auto-populated.   |

## Follow Up Tab

The fields on this tab describe follow-up entries for a case.

| Field               | Description   |
|---------------------|---|
| Actions Taken       | This text field can contain up to 4,000 characters. |
| Planned Actions     | This text field can contain up to 4,000 characters. |
| Recommended Actions | This text field can contain up to 4,000 characters. |
| Follow-up Contact   | This text field can contain up to 4,000 characters. |


## Final Tab

Fields on this tab provide ticket resolution and reporting information related to the attack agent associated with a case.

| Field                   | Description  |
|-------------------------|--|
| Attack Mechanism        |  |
| Attack Mechanism        | This field is auto-populated.  |
| Attack Protocol         | The network protocol that is transporting the attack.                                      |
| Attack OS               | The operating system supporting the attack.  |
| Attack Program          | The program that is performing the attack.   |
| Attack Time             | The date and time of the attack.   |
| Attack Target           | The host or device at which the attack is directed.  |
| Attack Service          | The service at which the attack is directed.   |
| Attack Impact           | The effect of the attack.  |
| Final Report Action     | The action recommended for this case.  |
| Attack Agent            |  |
| Attack Agent            | This field is auto-populated.  |
| Attack Location ID      | A short description of the location under attack, of up to 255 characters.                 |
| Attack Node             | A short description of the network node under attack, of up to 255 characters.             |
| Attack Address          | A text field in which you can record the IP address under attack, of up to 255 characters. |
| Incident Information    |  |
| Incident Source 1       | This field is auto-populated.  |
| Incident Source 2       | This field is auto-populated.  |
| Incident Source Address | A text field in which you can record up to 200 characters.                                 |
| Vulnerability           |  |
| Vulnerability           | This field is auto-populated.  |
| Vulnerability Type 1    | Selections include: Accidental or Intentional.   |

| Field                  | Description  |
|------------------------|--|
| Vulnerability Type 2   | Selections include: EMI/RFI, Insertion of Data, Theft of Service, Unauthorized, Probes, Root Compromise, DoS Attack, User Account. |
| Vulnerability Evidence | This text field can contain up to 4,000 characters.  |
| Vulnerability Source   | This text field can contain up to 4,000 characters.  |
| Vulnerability Data     | This text field can contain up to 4,000 characters.  |
| Other                  |  |
| History                | Selections include: Known Occurrence and Unknown.  |
| No. Occurrences        | A numeric value; the number of occurrences of the incident.  |
| Last Occurrence Time   | The date and time of the most recent incident.   |
| Resistance             | Selections include: High, Low, and Unknown.  |
| Consequence Severity   | This field is auto-populated.  |
| Sensitivity            | This field is auto-populated.  |
| Recorded Data          | This text field can contain up to 4,000 characters.  |
| Inspection Results     | This text field can contain up to 4,000 characters.  |
| Conclusions            | This text field can contain up to 4,000 characters.  |

## Events Tab


You can add events to a case from the Active Channels page () , as described in Using Active Channel Grids. The system then displays these events on the Cases Events tab.

| Field                         | Description   |
|-------------------------------|---|
| Description                   | This field is auto-populated from events included in a case.                            |
| Event Info and Payload fields | For selected events, this field displays event values and payload fields, if available. |

Events related to a use case are preserved in the case for tracking purposes even after the time period where the events would typically *age out* of the database.

## Attachments Tab


The Attachments tab shows files associated with the selected case. Click the **Attach** button to attach another file to the case.

If you do not see files as expected, try clicking the Refresh button () to update the view to show recently added files.

| Field                       | Description  |
|-----------------------------|--|
| Local file                  | Select this option to choose a file on your local system. Specify values for the following fields, which are displayed when you choose a local file:                                     |
| Name                        | A descriptive name for the file. This name can differ from the actual file name, and can include spaces. If you do not provide an alternative name here, the original file name is used. |
| Description                 | A text description of the file.  |
| File                        | Click Browse and use the file browser to navigate to and select the local file you want to attach to the case. (This field requires user input.)   |
| Text Encoding               | Encoding type. The default is ISO-8859-1.  |
| Share this file in ArcSight | Click this option if you want to make the file available as a shared resource on the ArcSight Manager.   |
| ArcSight file               | Select this option to choose a file on the ArcSight Manager.   |
| Files to attach             | Click the plus button next the drop-down menu to show the file browser on the ArcSight Manager. Navigate to and select a file on the ArcSight Manager. (This field requires user input.) |

Click **Attach** to attach the file to the case. (Or click Cancel to abandon attachment edits.)

Click **Submit** to save the case with the new attachment, the same way you save new settings on the other tabs.

Once the file is attached, anyone viewing the case can view details about the file and download it. To do this, navigate to a case, and click the Attachments tab. To view more details about an attachment, click the file name. To download an attachment, click the Download button () for that file.

## Notes Tab

| Field | Description   |
|-------|---|
| Note  | Use this field to record notes of up to 4,000 characters. |

## Chapter 6

# Handling Notifications

---

The Notifications feature displays notifications relevant to you that were triggered by certain event conditions.

The notifications on the display are grouped according to workflow-style stages such as pending, acknowledged, resolved, or informational. The specific groups you see have been tailored to your enterprise.

To see the details of a notification, click its listing in the relevant group.

| Notification Categories | Use   |
|-------------------------|---|
| Pending                 | These are notifications that you have not yet handled (reassigned to one of the following categories). Pending notifications older than 24 hours are automatically refiled as Not Acknowledged. |
| Acknowledged            | These are notifications to which you have responded.  |
| Not Acknowledged        | Pending notifications that go unacknowledged or unresolved for more than 24 hours are automatically refiled as Not Acknowledged.  |
| Resolved                | These are notifications for which you or a colleague have found a resolution and so have marked the notification accordingly.   |
| Informational           | These are notifications that are provided for information purposes only and do not require resolution or response.  |



## Chapter 7

# Using Reports

---

The ArcSight Web interface enables you to run reports, and view and save the report results.

The reports available to you are organized in the Cases resource tree on the left. Click the group folders in the tree to open or close them. Click a folder to see a list of its cases in the right-hand pane. Click the arrow icon in the upper-right corner of the resource pane to hide it or show it.

[“Running and Viewing Reports” on page 103](#)

[“Running and Saving Archived Reports” on page 103](#)

[“Report Parameters” on page 104](#)

[“Viewing Archived Reports” on page 105](#)

[“Advanced Configuration for Report Performance” on page 106](#)

## Running and Viewing Reports

To run and view a report

- 1 Click **Report Definitions** just below the toolbar.
- 2 Navigate to a report in the resource tree.
- 3 Click a report definition name to show it in the right pane.
- 4 Use the values already defined for the report's parameters or change them as necessary. (See [“Report Parameters” on page 104.](#))
- 5 Click **Run Report** to run the report and display the results.

If you are running the context report from the event inspector, click **View Report** to run and display the report.

---

For tips about how to run large reports that make efficient use of system resources, see [“Advanced Configuration for Report Performance” on page 106.](#)

---

## Running and Saving Archived Reports

To run and save a report

- 1 Click **Report Definitions** just below the toolbar.

- 2 Navigate to a report in the resource tree.
- 3 Click a report definition name to show it in the right pane.
- 4 Use the values already defined for the report's parameters or change them as necessary. (See ["Report Parameters" on page 104.](#))
- 5 Select the **Save Output** checkbox to expose the archive report detail fields.

If you are archiving the context report from the event inspector, click **Archive Report**. The report will generate and be displayed in the viewer panel. You can save the report output using the browser Save As function.

- 6 Enter the following details for saving the report output as an archived report and click **Run Report**:

| Field                          | Enter this  |
|--------------------------------|---|
| Archive Report Folder          | Browse to an existing folder in the ArcSight file system to save the report results. This makes the report results retrievable from the Archived Reports view later.<br><br>If you do not select a folder, you can save the report once the results are displayed using the save method that applies to the report format. For example, if you chose PDF, you can use the PDF save to save the results. |
| Archive Report Name            | Accept the default report name or enter a name for the saved report results. Spaces are OK.   |
| Archive Report Expiration Time | Accept the default date (6 months from today), or enter a date when the archived report results are deleted. <a href="#">\$NOW</a> indicates that the report results will be deleted when you close the report results viewer.  |

## Report Parameters

The following parameters are common to most reports. Depending on the query used as the source for a report, other parameters may be exposed here. For example, a report might prompt for a Start and End Date (timestamps) over which to run the report.

| Parameter     | Use  |
|---------------|--|
| Report Format | The format in which to generate the report. Note that RTF appears by default in Word documents, XLS in Excel worksheets, CSV in Excel worksheets, and PDF and HTML in browser windows. The CSV-Plain format intentionally has fewer report header lines.             |
| Page Size     | Choose a standard paper size for the printed report (whether you send it directly to print or not).  |
| Run as User   | As an option, choose an existing ArcSight user's identity as a report constraint. The user identity can serve as a type of filter on the report's output, or it may be desirable to run a report on behalf of a user, as in a provider/customer (MSSP) circumstance. |
| E-mail to     | Select one or more e-mail addresses to send notifications to when the report runs.   |
| E-mail Format | Choose to send the generated report or a URL to the file.  |



| Parameter                      | Use   |
|--------------------------------|---|
| Save Output                    | <p>Select this option to save the generated report to the ArcSight Manager as an Archived Report.</p> <p>When you select the Save Output option (toggled "on"), provide the name, location, and expiration date of the archived report.</p>   |
| Archive Report Folder          | Indicate the name of the folder in which you want to store the report.  |
| Archive Report Name            | <p>Enter the name of the report. You can use Velocity Template references here. By default, the report names is set to:</p> <p><code>\${Today}/\${ReportName}_\${Now}</code></p> <p><b>\$CurrentDateTime</b>: Prints the current date and time. (Same as \$Now)</p> <p><b>\$CurrentDate</b>: Prints the current date.</p> <p><b>\$CurrentMonth</b>: Prints the current month.</p> <p><b>\$CurrentWeek</b>: Prints the current week.</p> <p><b>\$Now</b>: Prints the current date and time. (Same as \$CurrentDateTime)</p> <p><b>\$CurrentDateTime-&lt;Number&gt;</b>: Prints the current date and time minus the number of days you specify.</p> |
| Archive Report Expiration Time | Enter an expiration date and time for the archived report. Click the calendar button next to the date field to get a popup calendar in which to designate the date. The ArcSight system automatically removes expired reports.  |

## Viewing Archived Reports

To view an archived report

- 1 Click **Archived Reports** just below the toolbar.
- 2 Navigate to a report in the resource tree.
- 3 Click the name of an archived report to show it in the right pane.

## Downloading an Archived Report

To download an archived report

- 1 Click **Archived Reports** just below the toolbar.
- 2 In the Download column for the report archive you want, click the **Download** icon.
- 3 In the File Download dialog box, choose to open the file or save it to a particular location.

## Adding New Archived Reports

To add a new archived report to a folder

- 1 Click **Archived Reports** just below the toolbar.
- 2 In the resource tree, select the report folder to which you want to add the new archived report.

- 3 Above the list of available reports, click **New Report**.
- 4 In the Upload Report screen, enter a report name and specify the path to its file, or click **Browse** to locate it.
- 5 Click **Upload** to add the archived file to the others available in the folder.

## Deleting Archived Reports

To delete archived reports

- 1 Click **Archived Reports** just below the toolbar.
- 2 Navigate to a report folder in the resource tree.
- 3 In the list of archived reports on the right, check those you want to delete.
- 4 Click **Delete** to remove the checked reports, then click **OK** to confirm.

## Advanced Configuration for Report Performance

Reports with large file sizes or large time ranges may require special configurations at the Manager to ensure system performance.

Set these parameters only as needed if you encounter large or complex reports that repeatedly cause performance problems or cause the Manager to restart when you try to run them. Refer to the *ArcSight Administrator's Guide* for more information on setting server properties on the Manager. The properties described here are also documented in the `server.properties` file itself.

### Configurations for Large Reports

A very large report (for example, a 500 MB PDF report) might require so much virtual machine (VM) memory that it can cause the ArcSight Manager to crash and re-start.

To prevent that, set up the Manager to expose a special report parameter for generating the report in a separate process. The separate process has its own VM and heap, so the report is more likely to finish. Even if the memory allocated is still not enough, the report failure will not crash the Manager.

This option must be set up on the ArcSight Manager to expose it in the ArcSight Web report parameters list. On the ArcSight Manager in the `server.properties` file, set `report.canarchiveinseparateprocess=true`. Save the `server.properties` file and restart the Manager.

Once this property is set to "`true`" on the Manager, the Save Output options for a selected report on ArcSight Web include a new parameter called *Generate Report In Separate Process*. Select this option for a report you want to archive as a separate process, and run the report.

If a report is saved with the parameter set to "`true`", the report is archived as a separate process even if the property `report.canarchiveinseparateprocess` in `server.properties` is set back to "`false`" later on.

## Configurations for Reports with Large Time Ranges

Reports that query over a large time range with complex joins run much faster if the query contains a full scan database hint. This option must be set up on the Manager to expose it in the ArcSight Web report parameters list.

On the ArcSight Manager in the `server.properties` file, set `report.canquerywithfullscanhint=true`. Save the `server.properties` file and restart the Manager.

Once this property is set to "true" on the Manager, the Save Output options for a selected report on ArcSight Web include a new parameter called *Query with Full Scan Hint*. Select this option for a report you want to run with the full scan hint, and run the report.

If a report is saved with the parameter set to "true", the report is archived as a separate process even if the property `report.canquerywithfullscanhint` in `server.properties` is set back to "false" later on.



## Chapter 8

# Monitoring Dashboards

---

The ArcSight Web interface enables you to view dashboards made available from the ESM Console.

When you click **Dashboards** in the toolbar, you see the Dashboards display, usually with the Dashboards tree open in the resource pane and the dashboards of the current branch listed in the content pane.

[“Viewing and Managing Dashboards” on page 109](#)

[“Changing Dashboard Layouts” on page 109](#)

## Viewing and Managing Dashboards

The dashboards are organized in the resource tree on the left. Click the group folders in the tree to open or close them. Click a folder to see a list of its dashboards in the pane to the right. Click the arrow icon in the upper-right corner of the resource pane to hide or show it.

Click a dashboard's name to open it and its collection of data monitors in the right pane.

By default, the information on a dashboard refreshes automatically every 60 seconds. Click the "Pause" button (| |) to stop refreshing, or click the circular arrow to refresh immediately. Click the arrow head to resume auto-refreshing.

Run the mouse pointer over elements in graphic data monitors to see their details in tooltips.

Three types of data monitors are available through ArcSight Web: Event Graph, Geographic Event Graph, and Hierarchy Map.

## Changing Dashboard Layouts

You can change the way data monitors are laid out on dashboard displays. When you click **Dashboards** and choose one to show from the resource tree, the layout of data monitors in the right panel is a default pattern.

In a dashboard display, click **Edit Layout** to open the Dashboard Layout editor.

To rearrange data monitors, click and drag them from one of the display areas to another. The upper and lower "wide" areas are intended to better accommodate tables, which most often run wide and cannot be resized. The left and right "narrow" areas are intended to accommodate charts, which are more likely to resize successfully.

To see a rearrangement, click **Save**.



## Chapter 9

# Using the Knowledge Base

---

ArcSight Web provides access to viewing knowledge base articles. The articles available to you are organized in the resource tree on the left. Click the folders in the tree to open or close them. Click the arrow icon in the upper-right corner of the resource tree panel to hide it or show it.



ArcSight offers the Knowledge Base as a convenience for storing user-generated pointers or articles of interest. It is not pre-populated.

---





## Using Reference Pages

---

An event viewed from the Event Inspector may have a reference page associated with it. The contents of a reference page is set through the ArcSight Console.

- If present in an event, click **View references** to show the reference page content in a separate browser window.
- Use the drop-down menu to navigate or other pages of this reference if more pages are available.
- Use the browser's **Back** button to return.



## Chapter 11

# Setting Preferences

---

In any display, click **Options** in the toolbar to set or change your preferences for date formatting, locale, active channel startup, and password.

Click the **Formats** tab to choose the style and punctuation to use for date and time values. Click **Update** to apply your changes before moving to another tab.

Click the **Locale** tab to choose the time zone you work in. Click **Update** to apply your changes before moving to another tab.

Click the **Channels** tab to set, or bypass setting, the parameters for active channels, each time you open one. The check box is clear by default, which means that you will see the channel setup options. Select the check box to avoid setup and to go directly to the channel display. There is also an option to hide (collapse) the channel tree on the left panel when a channel is already running. By default, this tree remains in view. Click **Update** to apply your changes before moving to another tab.

Click the **Password** tab to change your current password. Enter your old password first. Then enter your new password and repeat it to confirm. Click **Update** to put your change into effect.



## Chapter 12

# Custom Branding and Styling

---

You can change logo images, colors, and styles for ArcSight Web by creating and editing the file `<ArcSightWeb_HOME>/config/web/styles.properties`.

This file doesn't exist by default, but you can create it by copying either `example.styles.properties` or `full.styles.properties` and renaming it to `styles.properties`.



Please do not modify the file `<ArcSightWeb_HOME>/config/web/styles.defaults.properties`. This file contains the default settings. It will be overridden by your custom `styles.properties` file.

The properties file provides information about those properties that can be changed, along with example values.

To add custom branding or styles:

- 1 Modify the properties in `styles.properties` as needed to fit your custom branding and style requirements, and remove the comment tags from the lines that contain property settings you want to apply.
- 2 If you want to add one or more custom logo images as part of your re-branding effort, you will need to both both modify the relevant property settings and add the image(s) to the `webapp/images` directory:
  - ◆ Modify the properties file to call your custom image file(s) and un-comment the relevant lines (e.g., `navbarLogoImg=MyCustomLogo.gif` and `loginLogoImg=logo-login-MyCustomLogo.gif`). You might also want to modify and un-comment the logo image size property and navigation bar text colors to make the proper customizations.
  - ◆ Add the image file to the directory `<ArcSightWeb_HOME>/webapp/images`.
- 3 Restart ArcSight Web to see the effects of your custom changes.

Remember that branding changes are visible to anyone using that instance of ArcSight Web. You can, however, run multiple instances of ArcSight Web against the same ArcSight Manager.



# Index

---

## A

- Active Channels 17
  - Grids 19
  - Headers 19
  - Inline Filters 21
  - Opening 17
  - Viewing 19
- Archived Reports
  - Saving 103
  - Viewing 105
- ArcSight
  - Contact 2
- ArcSight Express 11
  - Getting Started with ArcSight Express 13
  - Home Page 12
  - Monitoring 14
  - Reporting 16
- ArcSight Web
  - About 5
  - Navigating 7
- Audit Events 76

## B

- Branding 117

## C

- Cases 93
  - Attachments tab 99
  - Columns 94
  - Events Tab 99
  - Final Tab 98
  - Follow Up tab 97
  - How to create 95
  - Initial Tab 95
  - Notes Tab 100
  - Security Classification Codes 94
- Channels 17
  - Preferences 115
- Contact ArcSight 2
- Content
  - ArcSight Express 11

## D

- Dashboards 109
  - Changing Layouts 109
  - Viewing and Managing 109
- Data Fields 30

## E

- Events
  - Audit Events 76
  - Data Fields 30
  - Event Categories 23
  - Events in cases 99
  - Inspecting 22

## F

- Formats
  - Preferences 115

## G

- Getting Started
  - with ArcSight Express 13

## H

- Home Page 7
  - ArcSight Express Home Page 12

## I

- Inline Filters 21
- Inspecting Events 22

## K

- Knowledge Base 111

## L

- Locale
  - Preferences 115
- logo
  - customizing 117

## M

- Monitoring
  - Active Channels 17
  - ArcSight Express 14
  - Dashboards 109
  - Inspecting Events 22

## N

- Navigating ArcSight Web 7
  - ArcSight Express Home Page 12
  - Basic Navigation 8
  - Home Page 7

Notifications 101

## **O**

Options 115

## **P**

Password

    Changing 115

Preferences 115

## **R**

Reference Pages 113

Reporting

    with ArcSight Express 16

Reports 103

    Advanced Configuration 106

    Parameters 104

    Running and Viewing 103

    Saving Archived Reports 103

    Viewing Archived Reports 105

## **S**

    see Active Channels 17

    styles.properties 117