



SERENA[®]
ChangeMan[®] ZMF 8.1

ERO Messages

Serena Proprietary and Confidential Information

Copyright © 2012-2015 Serena Software, Inc. All rights reserved.

This document, as well as the software described in it, is furnished under license and may be used or copied only in accordance with the terms of such license. Except as permitted by such license, no part of this publication may be reproduced, photocopied, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, recording, or otherwise, without the prior written permission of Serena. Any reproduction of such software product user documentation, regardless of whether the documentation is reproduced in whole or in part, must be accompanied by this copyright statement in its entirety, without modification.

This document contains proprietary and confidential information, and no reproduction or dissemination of any information contained herein is allowed without the express permission of Serena Software.

The content of this document is furnished for informational use only, is subject to change without notice, and should not be construed as a commitment by Serena. Serena assumes no responsibility or liability for any errors or inaccuracies that may appear in this document.

Trademarks

Serena, TeamTrack, StarTool, PVCS, Comparex, Dimensions, Prototype Composer, Mariner, and ChangeMan are registered trademarks of Serena Software, Inc. The Serena logo and Version Manager are trademarks of Serena Software, Inc. All other products or company names are used for identification purposes only, and may be trademarks of their respective owners.

U.S. Government Rights

Any Software product acquired by Licensee under this Agreement for or on behalf of the U.S. Government, its agencies and instrumentalities is "commercial software" as defined by the FAR. Use, duplication, and disclosure by the U.S. Government is subject to the restrictions set forth in the license under which the Software was acquired. The manufacturer is SERENA Software, Inc., 1850 Gateway Drive, Suite 150, San Mateo, California 94404 USA

Publication date: November 2015

Table of Contents

	Welcome to ChangeMan ZMF ERO	5
	Guide to ChangeMan ZMF Documentation	5
	ChangeMan ZMF Documentation Suite	5
	Using the Manuals	7
<i>Chapter 1</i>	ChangeMan ZMF ERO Messages	9
	Message Format	10
	Message Descriptions	10
	Release Management General Messages	10
	Release Management Administration Messages	11
	Release Management Audit Messages	13
	Release Management Block Messages	14
	Release Management Backout Messages	15
	Release Management Checkin Messages	15
	Release Management Generate Messages	20
	Release Management Install Messages	21
	Release Management Retrieve Messages	21
	Release Management Unblock Messages	22
	Release Management Housekeeping Messages	22
	Release Management Library Type Messages	22
	Release Management Approval Messages	23
	Release Management Checkout Messages	26
	Release Management Area Messages	26
	Release Packages Messages	28
	Release Management General Services Messages	30
	Release Management Query Messages	31
	Release Area Promotion Messages	31
	Index	35

Welcome to ChangeMan ZMF ERO

The purpose of this manual is to describe system messages and codes produced by ChangeMan[®] ZMF Enterprise Release Option (ERO).

Audience and scope This document is intended for ChangeMan ZMF ERO users, administrators, and the technical staff who install and support ChangeMan ZMF ERO software.

Change bars in the left margin (like that shown at left) identify substantive changes to this publication in ChangeMan ZMF ERO release 8.1.

Guide to ChangeMan ZMF Documentation

The following sections provide basic information about ChangeMan ZMF documentation.

ChangeMan ZMF Documentation Suite

The ChangeMan ZMF documentation set includes the following manuals in PDF format.

Manual	Description
<i>Administrator's Guide</i>	Describes ChangeMan ZMF features and functions with instructions for choosing options and configuring global and application administration parameters.
<i>ChangeMan ZMF Quick Reference</i>	Provides a summary of the commands you use to perform the major functions in the ChangeMan ZMF package life cycle.
<i>Customization Guide</i>	Provides information about ChangeMan ZMF skeletons, exits, and utility programs that will help you to customize the base product to fit your needs.
<i>DB2 Option Getting Started Guide</i>	Describes how to install and use the DB2 Option of ChangeMan ZMF to manage changes to DB2 components.
<i>ERO Concepts</i>	Discusses the concepts of the ERO Option of ChangeMan ZMF for managing releases containing change packages.
<i>ERO Getting Started Guide</i>	Explains how to install and use the ERO Option of ChangeMan ZMF to manage releases containing change packages.
<i>ERO Messages</i>	Describes system messages and codes produced by ChangeMan ZMF ERO.
<i>ERO XML Services User's Guide</i>	Documents ERO functions and services available for general customer use. These services are also known as the green services and provide primarily search and query functions.

Manual	Description
<i>High-Level Language Functional Exits Getting Started Guide</i>	Provides instructions for implementing and using High-Level Language (Cobol, PL/1, and REXX) exits, driven consistently by all clients to enforce local business rules in ZMF functions.
<i>IMS Option Getting Started Guide</i>	Provides instructions for implementing and using the IMS Option of ChangeMan ZMF to manage changes to IMS components.
<i>INFO Option Getting Started Guide</i>	Describes two methods by which ChangeMan ZMF can communicate with other applications: <ul style="list-style-type: none"> ■ Through a VSAM interface file. ■ Through the Tivoli Information Management for z/OS product from IBM.
<i>Installation Guide</i>	Provides step-by-step instructions for initial installation of ChangeMan ZMF. Assumes that no prior version is installed or that the installation will overlay the existing version.
<i>Java / HFS Getting Started Guide</i>	Provides information about using ZMF to manage application components stored in UNIX System Services (USS) file systems, especially Java application components.
<i>Load Balancing Option Getting Started Guide</i>	Explains how to install and use the Load Balancing Option of ChangeMan ZMF to connect to a ZMF instance from another CPU or MVS image.
<i>M+R Getting Started Guide</i>	Explains how to install and use the Merge and Reconcile (M+R) Option of ChangeMan ZMF to consolidate multiple versions of source code and other text components.
<i>M+R Quick Reference</i>	Provides a summary of M+R Option commands in a handy pamphlet format.
<i>Messages</i>	Explains messages issued by ChangeMan ZMF, SERNET, and System Software Manager (SSM) used for the Staging Versions feature of ZMF.
<i>Migration Guide Versions 6.1 and 7.1 to Version 8.1</i>	Gives guidance for upgrading ChangeMan ZMF from Versions 6.1.x and 7.1.x to Version 8.1.
<i>OFM Getting Started Guide</i>	Explains how to install and use the Online Forms Manager (OFM) option of ChangeMan ZMF.
<i>SER10TY User's Guide</i>	Gives instructions for applying licenses to enable ChangeMan ZMF and its selectable options.
<i>User's Guide</i>	Describes how to use ChangeMan ZMF features and functions to manage changes to application components.
<i>XML Services User's Guide</i>	Documents the most commonly used features of the XML Services application programming interface to ChangeMan ZMF.
<i>ZMF Web Services User's Guide</i>	Documents the Web Services application programming interface to ChangeMan ZMF.

Using the Manuals

The ChangeMan ZMF ERO manuals use the Adobe Portable Document Format (PDF). To view PDF files, use Adobe® Reader®, which is freely available from www.adobe.com.



TIP

Be sure to download the *full version* of Reader. The more basic version does not include the search feature.

This section highlights some of the main Reader features. For more detailed information, see the Adobe Reader online help system.

The PDF manuals include the following features:

- **Bookmarks.** All of the manuals contain predefined bookmarks that make it easy for you to quickly jump to a specific topic. By default, the bookmarks appear to the left of each online manual.
- **Links.** Cross-reference links within an manual enable you to jump to other sections within the manual and to other manuals with a single mouse click. These links appear in blue.
- **Printing.** While viewing a manual, you can print the current page, a range of pages, or the entire manual.
- **Advanced search.** Starting with version 6, Adobe Reader includes an advanced search feature that enables you to search across multiple PDF files in a specified directory. (This is in addition to using any search index created by Adobe Catalog—see step 3 below.)

To search within multiple PDF documents at once, perform the following steps (requires Adobe Reader version 6 or higher):

- 1 In Adobe Reader, select Edit | Search (or press CTRL+F).
- 2 In the text box, enter the word or phrase for which you want to search.
- 3 Select the **All PDF Documents in** option, and browse to select the folder in which you want to search.
- 4 Optionally, select one or more of the additional search options, such as **Whole words only** and **Case-Sensitive**.
- 5 Click the **Search** button.



NOTE

Optionally, you can click the **Use Advanced Search Options** link near the lower right corner of the application window to enable additional, more powerful search options. (If this link says **Use Basic Search Options** instead, the advanced options are already enabled.) For details, see Adobe Reader's online help.

Chapter 1

ChangeMan ZMF ERO Messages

This chapter describes ISPF messages issued by the ERO option of Serena ChangeMan ZMF.

If you are reading this book from hardcopy, use the Index to locate a message number. If you are viewing this book as a PDF file, use the Find function in your viewer to locate a message.

Message Format	10
Message Descriptions	10

Message Format

Each ISPF message can have two forms: a short message and a long message explanation.

The short message automatically displays in the upper right corner of the panel, overlaying any panel text in that area. See [1] in the sample panel below. The long message, which is more descriptive, displays when you press the PF1 HELP key after the short message displays. See [2] in the third line of the sample panel below.

```
CMRpanel ----- title of panel ----- short [1] message
COMMAND ==>
CMRnnnnx - [2]..long message
panel text
```

The first three characters identify the application CMR, which stands for ChangeMan ZMF ERO. The next four digits *nnnn* refer to the message number. Use the message number to find an explanation for the message in this manual, or to request support from Serena Customer Support.

The last character, *x*, refers to the type of message:

- A refers to error messages that require Action.
- I refers to Informational messages that acknowledge the completion of a task.

Message Descriptions

The message descriptions list both the short and the long versions of the message, separated by the OR character, "|", for example,

Process Error | Release {*release*} - backout is already in progress.

The position of a variable value such as the release number are indicated by variable names enclosed in braces and italicized, for example, {*release*}.

Release Management General Messages

CMR0001I	Invalid Status Invalid Release status { <i>release</i> } must be in { <i>status</i> } status.
CMR0002I	Release Undefined Package { <i>package</i> } not defined to a Release or Area.
CMR0003A	Invalid Status Invalid Release status { <i>status</i> } - must be in APR, REJ, DIS or BAK status.
CMR0004I	No Prior Release No Prior Releases found for release { <i>release</i> } Application { <i>application</i> }.

CMR0005I	No Releases Found No Other Releases found for Application <i>{application}</i> .
CMR0006A	Release Already Defined Release <i>{release}</i> has already been defined.
CMR0007A	Global Parm's Updated Release Global Parameters have been successfully updated.
CMR0008A	Option not Available Release Management is not licensed, contact administrator.
CMR0009A	Invalid Status Invalid Release status <i>{status}</i> - must be in BAS or INS status.
CMR0010A	Process Error Release <i>{release}</i> - install is already in progress.
CMR0011A	Process Error Release <i>{release}</i> - backout is already in progress.
CMR0012I	Invalid Name Invalid Release name specified, must begin with an alpha (A-Z).
CMR0013I	Release Already Defined Release <i>{release}</i> has already been defined copy not allowed.
CMR0014I	Not a Prior Release Release <i>{release}</i> has an install date greater than <i>{date}</i> .

Release Management Administration Messages

CMR0500A	Undefined Release Release <i>{release}</i> is undefined - contact Release Admin.
CMR0501A	Undefined Application Undefined application <i>{application}</i> - contact local ADMIN.
CMR0502A	Application Locked Application <i>{application}</i> globally locked for update.
CMR0503A	Undefined Prior Release Undefined Prior Release <i>{release}</i> - contact Release ADMIN.
CMR0504A	Invalid Install Date Release Install Date must be current or future.
CMR0505A	Invalid Install Date Release Install to Date must be greater than from Date.
CMR0506A	Invalid Install Time Release Install to Time must be greater than from Time.
CMR0507A	Invalid Install Time Release Install Time must be 000000 to 235959 in hhmmss.
CMR0510A	Authorization Failed You must have Global, Local, or RlseMgr authority to enter Admin.

CMR0511A	Authorization Failed You must have Global or Release Manager Authority.
CMR0512A	Authorization Failed You must have Global or Release Manager Authority.
CMR0513A	Authorization Failed You must have Global Admin Authority to define the global HLQ.
CMR0515A	Authorization Failed Your TSOID is not authorized to create the approval entity.
CMR0516A	Invalid Entity Name Approval entity name is not defined in the security system.
CMR0517A	Invalid Area Rule Area Rule, { <i>arearule</i> } can not be less than Release Rule { <i>releaserule</i> }.
CMR0518I	Applications Found Release { <i>release</i> } still has applications attached.
CMR0519A	No Prior Release There are no Prior Releases found for Release { <i>Release</i> }.
CMR0520A	No Applications There are no Applications attached to Release { <i>release</i> }.
CMR0521A	Release Created Release { <i>release</i> } has been successfully created.
CMR0522A	Release Updated Release { <i>release</i> } has been successfully updated.
CMR0523A	Release Deleted Release { <i>release</i> } has been successfully deleted.
CMR0524A	Release Undeleted Release { <i>release</i> } has been successfully undeleted.
CMR0525A	Release Updated Prior Release { <i>priorrelease</i> } has been successfully updated for Release { <i>updatedrelease</i> }.
CMR0526A	Prior Release Deleted Prior Release { <i>priorrelease</i> } has been successfully deleted for Release { <i>release</i> }.
CMR0527A	Application Joined Application { <i>application</i> } has been successfully joined release.
CMR0528A	Application Updated Application { <i>application</i> } has been successfully updated.
CMR0529A	Application Deleted Application { <i>application</i> } has been successfully deleted.
CMR0530A	Libraries Deleted Release { <i>release</i> } Area libraries successfully deleted.
CMR0531I	Invalid Name Invalid Area name specified, must begin with an alpha (A-Z).
CMR0532A	Undefined Approver Invalid Area name specified, must begin with an alpha (A-Z).

CMR0533A	Invalid Approver Global Approver { <i>approver</i> } is not a release install Approver.
CMR0534A	Invalid Approver Global Approver { <i>approver</i> } is not an area type approver.
CMR0535A	Invalid Approver Global Approver { <i>approver</i> } is an associated approver.
CMR0536A	Invalid Approver Global Approver { <i>approver</i> } is not an associated approver.
CMR0537A	Undefined Remote Site Undefined Remote Site { <i>site</i> } - contact global ADMIN.
CMR0538A	Invalid Release Rule Release Rule, { <i>releaserule</i> } can not be less than Global Rule { <i>globalrule</i> }.
CMR0539A	Invalid Install Time Release Install to Time must be 1 min. more then from Time.
CMR0540A	Scheduler Not Allowed Release Scheduler { <i>scheduler</i> } does not allow {??????} -contact Release ADMIN.
CMR0541A	Invalid Application Application { <i>invalidapp</i> } cannot have application { <i>relatedapp</i> } as a related application.
CMR0542A	Invalid Input Release and base ZMF applications are mutually exclusive.

Release Management Audit Messages

CMR1000I	Invalid Audit Level Audit level { <i>level</i> } invalid - should be 0 to 5.
CMR1001I	Audit Failure Area { <i>area</i> } failed the audit with a return code of { <i>code</i> }.
CMR1002I	Audit Failure Package { <i>package</i> } failed the audit with a return code of { <i>code</i> }.
CMR1003I	Audit Failure Area must be audited when audit rule is greater than 0.
CMR1004A	Audit Failure If using autoresolve area must first pass TestArea function.

Explanation: This is a SYSPRINT message from batch program CMNRA000, which executes a test area when release audit is submitted with the auto resolve option. The test area ensures that area components match the package libraries where they originated so that there is no possibility that auto resolve will overlay package components that have been changed or create orphans where package components have been deleted. This message indicates that the test area failed and that release audit with auto resolve is halted with RC=12.

Solution: Resolve the issues detected by test area, and then resubmit release audit with auto resolve.

- CMR1005I (No short message) | Autoresolve requested.
Explanation: This is a SYSPRINT message from batch program CMNRA000 to indicate that release audit was submitted with the auto resolve option.
Solution: None.
- CMR1006I (No short message) | Audited area has passed TestArea function, autoresolve will proceed.
Explanation: This is a SYSPRINT message from batch program CMNRA000, which executes a test area when release audit is submitted with the auto resolve option. The test area ensures that area components match the package libraries where they originated so that there is no possibility that auto resolve will overlay package components that have been changed or create orphans where package components have been deleted. This message indicates that test area was passed and that release audit with auto resolve will continue.
Solution: None.
- CMR1066I Undefined Security Entity | Security entity {*entity*} undefined; contact security ADMIN.
- CMR1090A Authorization Failed | Application access denied - contact local ADMIN.
- CMR1094A Unauthorized Access | {*entity*} entity authorization required.

Release Management Block Messages

- CMR1500A Invalid Blocking Rule | Blocking rule {*rule*} invalid - should be 0 - 3.
- CMR1501I Release Blocked | Release {*release*} has been successfully blocked.
- CMR1502I Area Blocked | Release {*release*} Area {*area*} has been successfully blocked.
- CMR1503I Audit Failure | Area must be audited when blocking rule is greater than 0.
- CMR1504A Authorization Failed | Release Manager Authority required to Block or Unblock.
- CMR1505A Authorization Failed | Release Manager Authority required to Revert.
- CMR1506I Components Failed | Release {*release/area*} and package components do not match.
Explanation: Test area failed, detecting differences between components in the indicated release area and the package libraries where the components originated.
Solution: Resolve the issues detected by test area. Resubmit test area or the function that you executed that initiated a test area, such as release audit with the auto resolve option.
- CMR1507I Components Passed | Release {*release*} and package components match.

CMR1527I Node Outstanding | Package *{package}* installation JCL build outstanding.

Release Management Backout Messages

CMR2000I Release Reverted | Release *{release}* has been successfully reverted.

CMR2001I Backouts Submitted | Release *{release}* package backouts have been submitted.

CMR2002I Backout Not Allowed | Package *{package}* is attached to release *{release}*, backout release.

Release Management Checkin Messages

CMR2500A Invalid Option | Release package is in *{status}* status - must be DEV, FRZ, or APR.

CMR2501A Package Not Found | Release package *{package}* does not exist in the package master.

CMR2502A Package Memo Deleted | Release package *{package}* is in memo deleted status.

CMR2503A Install Date Error | Package install date must be current or future for checkin.

CMR2504A Authorization Failed | Release application access denied - contact Release Admin.

CMR2505A Invalid Package Level | Release package level must be simple.

CMR2506A Invalid Package Id | Release package ID must be a planned permanent package.

CMR2507A Undefined Application | Undefined release application *{application}* - contact Release Admin.

CMR2508A No Components Found | No release package components found in the package master.

CMR2509A Storage Error | Memory unavailable for build of dynamic panel. Getmain RC = *{returncode}*.

CMR2510A Storage Error | Memory unavailable for build of component list. Getmain RC = *{returncode}*.

CMR2511A Invalid Date | *{date}* is an invalid Gregorian date for checkin function.

CMR2512A Invalid Date Range | FROM date *{date}* is more current than the TO date for checkin.

CMR2513I Select Error | Component override not allowed on a locked component.

CMR2514A	Release Undefined Package <i>{package}</i> not defined to a Release - contact Release Admin
CMR2515A	Release Invalid <i>{??????}</i> not defined to Release <i>{release}</i> - contact Release Admin.
CMR2516A	Area Invalid <i>{??????}</i> not defined to Area <i>{area}</i> - contact Release Admin.
CMR2517A	Area Undefined Package <i>{package}</i> not defined to an Area - contact Release Admin.
CMR2518A	Invalid Check-in Rule Check-in Rule <i>{rule}</i> invalid - should be 0 - 7.
CMR2519A	Run Table Error No entries found on select request to Baseline Unique Table.
CMR2520A	Storage Error Memory unavailable for build of Selection Idx. Getmain RC = <i>{returncode}</i> .
CMR2521A	DB2 Open Error Error attempting open of DB2 Call Attach Facility.
CMR2522A	DB2 Close Error Error attempting close of the DB2 Call Attach Facility.
CMR2523A	Storage Error Memory unavailable for build of Duplicate list. Getmain RC = <i>{returncode}</i> .
CMR2524A	Storage Error Memory unavailable for build of Duplicate Idx. Getmain RC = <i>{returncode}</i> .
CMR2525A	Storage Error Memory unavailable for build of Duplic panel. Getmain RC = <i>{returncode}</i> .
CMR2526I	Select Error Component override not allowed on a different release package
CMR2527I	Select Error Not all components displayed can be selected for override.
CMR2528I	Select Error Component override not allowed on lib type without a valid Bun.
CMR2529I	No Selections No components selected for Checkin into target area <i>{area}</i> .
CMR2530I	Not Qualified No components selected for Checkin qualify for area <i>{area}</i> .
CMR2531A	Rlse not Found Release Name Id <i>{id}</i> does not exist in the package master.
CMR2532A	Area not Found Release Area Id <i>{id}</i> does not exist in the package master.
CMR2533I	Action in Progress Checkin bypassed due to <i>{??????}</i> in progress for area <i>{area}</i> .

CMR2534I	Area Blocked Checkin bypassed for {??????} due to area {area} is blocked.
CMR2535A	Invalid Rule Invalid or conflicting checkin rules detected for area {area}.
CMR2536A	Rule Violation Checkin rule for area {area} requires {??????} to be frozen
CMR2537A	Storage Error Memory unavailable for build of Lib Type Table. Getmain RC = {returncode}.
CMR2538A	Storage Error Memory unavailable for build of Approval List. Getmain RC = {returncode}.
CMR2539A	No Approver Record Release Id {id} approver record not found in package master.
CMR2540A	No Approver Record Release Area {area} approver record not found in package master.
CMR2541A	Storage Error Memory unavailable for build of User List. Getmain RC = {returncode}.
CMR2542A	Storage Error Memory unavailable for build of Bun Table Area. Getmain RC = {returncode}.
CMR2543A	Storage Error Memory unavailable for build of Src-Lod List. Getmain RC = {returncode}.
CMR2544A	Storage Error Memory unavailable for build of Src-Lod panel. Getmain RC = {returncode}.
CMR2545I	Select Error Component override not allowed on a different user id.
CMR2546A	Storage Error Memory unavailable for build of UCA Work Area. Getmain RC = {returncode}.
CMR2547A	Package Master Error Global Record 0 not found during build of Release Area data sets.
CMR2548A	HLQ Not Found Release high level qualifier name not found in Global Record 0.
CMR2549A	Storage Error Memory unavailable for the area names table. Getmain RC = {returncode}.
CMR2550A	Library Error Release Id {id} lib type record not found in package master.
CMR2551A	Storage Error Memory unavailable for area dataset table. Getmain RC = {returncode}.
CMR2552A	No Area Libraries No release area library types defined in the package master.
CMR2553A	Storage Error Memory unavailable for area data set panel. Getmain RC = {returncode}.

CMR2554A	No Release Areas No release area names defined for Release Id {id}.
CMR2555A	Storage Error Memory unavailable for allocation progress. Getmain RC = {returncode}.
CMR2556A	I/O Error In progress indicator not set to ON due to Pmast I/O error.
CMR2557A	I/O Error In progress indicator not set to OFF due to Pmast I/O error.
CMR2558A	Storage Error Memory unavailable for checkin result list. Getmain RC = {returncode}.
CMR2559A	Copy Error Error on Copy to Target Area {area}.
CMR2560A	Storage Error Memory unavailable for summary panel area. Getmain RC = {returncode}.
CMR2561A	DB2 Error DB2 error attempting commit for delete of rows in CIM Table.
CMR2562A	DB2 Error DB2 error attempting commit for insert of rows in CIM Table.
CMR2563A	Storage Error Memory unavailable for member list lib Area. Getmain RC = {returncode}.
CMR2564A	List Error Error on member list for {??????}.
CMR2565A	Storage Error Memory unavailable for member list area. Getmain RC = {returncode}.
CMR2566I	Select Error Component override not allowed-member not found in data set.
CMR2567I	Select Error Component override not allowed-component authorization required.
CMR2568A	Storage Error Memory unavailable for component load area. Getmain RC = {returncode}.
CMR2569A	DB2 Error DB2 error attempting insert of history records in HST Table.
CMR2570A	DB2 Error DB2 error attempting commit for insert of rows in HST Table.
CMR2571A	I/O Error I/O error on log file attempting update for Checkin activity.
CMR2572A	Invalid Rule Invalid or conflicting Audit rules detected for area {area}.
CMR2573A	Invalid Job Card Change Man Exit 8 indicates invalid job card information.
CMR2574A	Ispfile Not Found {??????} ISPF FILE data set was not found.

CMR2575A	Ftopen Error Error on file tailoring open for skel {???????}. RC = {returncode}.
CMR2576A	Ftincl Error Error on file tailoring include for skel {???????}. RC = {returncode}.
CMR2577A	Ftclose Error Error on file tailoring close for skel {???????}. RC = {returncode}.
CMR2578A	Audit Submit Error Error on submit of audit job for target area {area}.
CMR2579I	Audit Job Submitted Job submitted to audit area {area} of release {release}.
CMR2580A	I/O Error I/O error on log file attempting update for Audit activity.
CMR2581A	Authorization Failed Release checkin entity access denied - contact Release Admin.
CMR2582A	Authorization Failed Release Id access denied - contact Release Administrator.
CMR2583A	Authorization Failed Release checkin entity not defined - contact Release Admin.
CMR2584A	Notification Error Release area {area} notification error for checkin approvers.
CMR2585I	Notify Action Area {area} of release {release} waiting for checkin approval request by user {userid}.
CMR2586A	Authorization Failed Release Id entity {???????} not defined - contact Rlse Admin.
CMR2587A	I/O Error Notify indicator not set for {???????} due to Pmast I/O error.
CMR2588A	Storage Error Memory unavailable for approver work area. Getmain RC = {returncode}.
CMR2589A	Notify Failed Checkin approval required, no approvers defined. Contact Rlse Admin.
CMR2590A	Notify Failed Checkin approval required, no users defined. Contact Rlse Admin.
CMR2591A	CAF Error DB2 CAF error processing {???????} request
CMR2592A	No Components Found No release components were found for area {area}.
CMR2592A	Checkin Not Approved Checkin approval required for area {area}. Contact Release Admin.
CMR2593A	Checkin Not Approved Checkin approval required for area {area}. Contact Release Admin.

CMR2594A	Rule Violation Checkin rule for area { <i>area</i> } requires {??????} to be blocked.
CMR2595A	Checkoff Not Approved Checkoff approval required for area { <i>area</i> }. Contact Release Admin.
CMR2595A	Checkin Not Allowed Checkin of final release area { <i>area</i> } not allowed.
CMR2596I	Checkin Not Allowed Checkin of final release area { <i>area</i> } not allowed.
CMR2597I	Audit Failure Area must be audited when check-in rule is 1, 4, 5 or 7.
CMR2598A	Rule Violation Checkin rule for area { <i>area</i> } requires {??????} to be frozen.
CMR2599I	Audit Failure Package must be audited when check-in rule is 1, 4, 5 or 7.
CMR2600I	Job Submitted Job to batch check-in has been submitted.
CMR2601A	DB2 Error Insert of i/a table records failed, see server SERPRINT for details.
CMR2602A	DB2 Error Delete of i/a table records failed, see server SERPRINT for details.
CMR2610I	Checkin Complete Checkin completed {??????} of {??????} components for area { <i>area</i> }.
CMR2700I	Select Error Component override not allowed, override not specified.
CMR2701I	Select Error Library Type BUN (Baseline Unique Number) for {??????} not found.
CMR2702I	Select Error Component {??????} is locked by {??????}.
CMR2730I	Checkin Exit Error Checkin halted by system exit, please contact administrator.
CMR2731I	No Component Found System exit removed all selected components, contact administrator.
CMR2800I	Select Error Source {??????} has related components checked in.

Release Management Generate Messages

CMR3000A	Invalid Generate Rule Generate Rule { <i>rule</i> } invalid - should be 0 - 6.
CMR3050I	Invalid Option No Area libraries to process.
CMR3292I	Promotion Error {??????} is currently promoted to this level {??????}.

Release Management Install Messages

- CMR3500I Undefined Install Site | Release Application *{application}* Install Site *{site}* not found.
- CMR3501A Invalid Option | Release Application *{application}* Install Site *{site}* not found.

Release Management Retrieve Messages

- CMR4000A Invalid Retrieve Rule | Retrieve Rule *{rule}* invalid - should be 0 - 3.
- CMR4001I Area Blocked | Retrieve bypassed for *{??????}* due to area *{area}* is blocked
- CMR4002A Invalid Rule | Invalid or conflicting retrieve rules detected for area *{area}*.
- CMR4003I Action in Progress | Retrieve bypassed due to *{??????}* in progress for area *{area}*
- CMR4004A Authorization Failed | Release retrieve entity access denied - contact Release Admin.
- CMR4005A Authorization Failed | Release retrieve entity not defined - contact Release Admin.
- CMR4006A Install Date Error | Package install date must be current or future date for retrieve.
- CMR4007A Invalid Date | *{date}* is an invalid Gregorian date for retrieve function.
- CMR4008A Invalid Date Range | FROM date *{date}* is more current than the TO date for retrieve.
- CMR4009I No Selections | No components selected for Retrieve from target area *{area}*.
- CMR4010A I/O Error | I/O error on log file attempting update for Retrieve activity.
- CMR4011A Storage Error | Memory unavailable for retrieve result list. Getmain RC = *{returncode}*.
- CMR4012A Delete Error | Error on Delete from Target Area *{area}*.
- CMR4013I Not Qualified | No components selected for Retrieve qualify for area *{area}*.
- CMR4014I No Component | Component *{??????}* not found for target area *{area}*.
- CMR4020I Job Submitted | Job to batch retrieve has been submitted.
- CMR4030I Retrieve Exit Error | Retrieve halted by system exit, please contact administrator.

- CMR4031I No Component Found | Retrieve halted by system exit, please contact administrator.
- CMR4040I Retrieve Complete | Retrieve completed {??????} of {??????} components for area {area}.
- CMR4210A INVALID DATE | {date} is an invalid Gregorian date.
- CMR4400I Release Detach Error | Package {package} still has components not retrieved from Release.
- CMR4401I Retrieve Error | Package {package} has no components to retrieve from Release.
- CMR4402I Release Detach Error | Package {package} has components in the Release, RP to Retrieve.

Release Management Unblock Messages

- CMR4500I Release Unblocked | Release {release} has been successfully unblocked.
- CMR4501I Area Unblocked | Release {release} Area {area} has been successfully unblocked.

Release Management Housekeeping Messages

- CMR5051A Versions not allowed | Save staging versions not allowed for RECFM "U" library types.
- CMR5052A Versions not allowed | Save staging versions not allowed for library type like other.

Release Management Library Type Messages

- CMR5500A Undefined Library Type | Library Type {type} is undefined for release {release}.
- CMR5501A Undefined Library Type | SYSLIB Library Type {type} is undefined.
- CMR5502A Not All Changes Allowed | Library Type(s) {type} area libraries already allocated.
- CMR5503I SYSLIB Not Found | SYSLIB definition for {??????} not found.
- CMR5504I Invalid SYSLIB Type | SYSLIB Library Type {type} has an invalid like Value {??????}.
- CMR5505I Invalid SYSLIB Type | SYSLIB Library Type {type} invalid for copylib request.
- CMR5506I Target LibType Error | Library Type {type} has no target library type defined.

CMR5507I	No More Library Types There are no more library types for related application found to add.
CMR5508A	No Library Types Added There are no more library types for related application found to add.
CMR5509A	No More Library Types There are no more {??????} library types found.
CMR5510A	No More Langs/Procs No more languages/procedures found for library type { <i>type</i> }.
CMR5511A	Library Type Updated Library Type { <i>type</i> } has been successfully updated.
CMR5512A	Library Type Deleted Library Type { <i>type</i> } has been successfully deleted.
CMR5513A	SYSLIB Updated SYSLIB {??????} has been successfully updated.
CMR5514A	SYSLIB Deleted SYSLIB {??????} has been successfully deleted.
CMR5515A	Undefined Lang/Proc Language/Procedure {??????} undefined for application { <i>application</i> }.
CMR5516A	Undefined LibType Application does not have release LibType { <i>libtype</i> } defined.
CMR5517A	Invalid Numeric Invalid numeric data {??????} for {??????}.
CMR5518A	Undefined Library Type Global Library Type { <i>type</i> } is undefined.
CMR5519A	Undefined Library Type Application { <i>application</i> } Library Type { <i>type</i> } is undefined.
CMR5520I	Invalid Library Type Only source library types have copylib concatenations.
CMR5521I	Libraries Allocated Release { <i>release</i> } area libraries allocated for library type { <i>type</i> }.

Release Management Approval Messages

CMR6000A	Invalid Approval Rule Approval Rule { <i>rule</i> } invalid - should be 0 - 3.
CMR6001A	Undefined Approver Approver entity {??????} is not defined contact Release Admin.
CMR6002A	Invalid Approver Code Approver code { <i>code</i> } is not valid, A and R are valid.
CMR6010A	Approver association Approver association does not exist for {??????}.
CMR6011I	Approval Error Approval/Rejection previously executed for this approver.

CMR6012I	Sequence Error Your approval/rejection is not next on the hierarchy list.
CMR6013I	Reject Not Found Release { <i>release</i> } has never been rejected.
CMR6014I	Reject Not Found Release { <i>release</i> } Area { <i>area</i> } has never been rejected.
CMR6015I	Already Notified Release { <i>release</i> } Area { <i>area</i> } approvers already notified.
CMR6016I	Invalid Value Check-in value { <i>value</i> } invalid, must be Y or N.
CMR6017I	Invalid Value Check-off value { <i>value</i> } invalid, must be Y or N.
CMR6018I	Invalid Approver Check-in and Check-off approvers are mutually exclusive.
CMR6019I	Invalid Approver Approver must be either a Check-in or Check-off approver.
CMR6020I	Invalid Value Associated value { <i>value</i> } invalid, must be Y or N.
CMR6021I	Invalid Value Install approver value { <i>value</i> } invalid, must be Y or N.
CMR6022I	Invalid Approver Approver must be either a Check-in, Check-off or Install approver.
CMR6023I	Invalid Association Approver association must have at least one association entered.
CMR6024I	Approver Error No Approvers Notified for release { <i>release</i> } Area { <i>area</i> }.
CMR6025A	Approvers Notified Updates for { <i>??????</i> } approvers denied already notified.
CMR6026A	Approver Already Defined Approver { <i>??????</i> } has already been defined.
CMR6027A	No Global Approvers There are no more Global Approvers to list.
CMR6028A	Global Approver Updated Global Approver { <i>??????</i> } has been successfully updated.
CMR6029A	Global Approver Created Global Approver { <i>??????</i> } has been successfully created.
CMR6030A	Global Approver Deleted Global Approver { <i>??????</i> } has been successfully deleted.
CMR6031A	Install Approver Updated Install Approver { <i>??????</i> } has been successfully updated.
CMR6032A	Install Approver Deleted Install Approver { <i>??????</i> } has been successfully deleted.

CMR6033A	Area Approver Updated Area Approver {??????} has been successfully updated.
CMR6034A	Area Approver Deleted Area Approver {??????} has been successfully deleted.
CMR6035I	Release Approved Approver {??????} has successfully approved Release { <i>release</i> }.
CMR6036I	Release Rejected Approver {??????} has successfully rejected Release { <i>release</i> }.
CMR6037I	Release Approved Release { <i>release</i> } has been approved.
CMR6038I	Release Rejected Release { <i>release</i> } has been rejected.
CMR6039I	Area Approvers Notified Release { <i>release</i> } Area { <i>area</i> } check-off approvers notified.
CMR6040I	Area Approvers Notified Release { <i>release</i> } Area { <i>area</i> } check-in approvers notified.
CMR6041I	Area Approvers Reset Release { <i>release</i> } Area { <i>area</i> } check-in approvers have been reset.
CMR6042I	Area Approved Approver {??????} has successfully approved Area { <i>area</i> }.
CMR6043I	Area Rejected Approver {??????} has successfully rejected Area { <i>area</i> }.
CMR6044I	Area Approved Release { <i>release</i> } Area { <i>area</i> } has been approved for check-in.
CMR6045I	Area Rejected Release { <i>release</i> } Area { <i>area</i> } has been rejected for check-in.
CMR6046I	Area Approved Release { <i>release</i> } Area { <i>area</i> } has been check-off approved.
CMR6047I	Area Rejected Release { <i>release</i> } Area { <i>area</i> } has been rejected for check-off.
CMR6048I	Invalid Approver Approver entity {??????} is not a Check-in approver.
CMR6049I	Invalid Approver Approver entity {??????} is not a Check-off approver.
CMR6050I	Invalid Approver Approver entity {??????} is not a Release approver.
CMR6051I	Area Approved Release { <i>release</i> } Area { <i>area</i> } has already been check-in approved.
CMR6052I	Area Approved Release { <i>release</i> } Area { <i>area</i> } has already been check-off approved.

Release Management Checkout Messages

CMR6500A	Invalid Option Release package is in {??????} status; must be in DEV status.
CMR6502I	Action in Progress Checkout bypassed due to {??????} in progress for area { <i>area</i> }
CMR6503A	Install Date Error Package install date must be current or future date for checkout.
CMR6504I	No Information No information found for {??????} request.
CMR6507A	Invalid Date { <i>date</i> } is an invalid Gregorian date for checkout function.
CMR6508A	Invalid Date Range FROM date { <i>date</i> } is more current than the TO date for checkout.
CMR6509I	No Selections No components selected for Checkout into target area { <i>area</i> }.
CMR6510A	I/O Error I/O error on log file attempting update for Checkout activity.
CMR6511A	Storage Error Memory unavailable for checkout result list. Getmain RC = { <i>returncode</i> }.
CMR6512A	Copy Error Error on Copy from Target Area { <i>area</i> }.
CMR6513A	No Library Types No application library types defined in the package master.
CMR6514A	Update Alloc Error Unable to update deferred allocation for {??????} library type.
CMR6515I	Not Qualified No components selected for Checkout qualify for area { <i>area</i> }.
CMR6516I	No Areas Found No Areas were found for release { <i>release</i> } that allow checkout.

Release Management Area Messages

CMR7000A	Undefined Area Area { <i>area</i> } is undefined for release { <i>release</i> } .
CMR7001I	Invalid Status Release { <i>release</i> } Area { <i>area</i> } is not blocked.
CMR7002I	Invalid Status Release { <i>release</i> } Area { <i>area</i> } is already blocked.
CMR7003I	Invalid Status Release { <i>release</i> } Area { <i>area</i> } has not been approved for check-in.
CMR7004A	Incomplete Areas No Subsystem Area found for Release { <i>release</i> }.
CMR7005A	Incomplete Areas No System Area found for Release { <i>release</i> }.

CMR7006A	Incomplete Areas No starting Subsystem Area found for Release { <i>release</i> }.
CMR7007A	Incomplete Areas No ending System Area found for Release { <i>release</i> }.
CMR7008A	Invalid Ending Area Areas can only have one ending System Area.
CMR7009A	Area Config. Invalid Area { <i>area</i> } is not a valid starting SubSystem Area.
CMR7010A	Undefined Area Area { <i>area1</i> } contains next/prior Area { <i>area2</i> } that is undefined.
CMR7011A	Area Config. Invalid Area { <i>area</i> } is not a valid ending System Area.
CMR7012A	Area Config. Invalid Area { <i>area</i> } can not have itself as a next/prior area.
CMR7013A	Area Config. Invalid Area { <i>area1</i> } Next Area { <i>area2</i> } is not a higher step number.
CMR7014A	Area Config. Invalid Area { <i>area1</i> } Prior Area { <i>area2</i> } is not a lower step number.
CMR7015A	Area Config. Invalid System Area { <i>area1</i> } can not have Subsystem Area { <i>area2</i> } as Next Area.
CMR7016A	Area Config. Invalid Subsystem Area { <i>area1</i> } can not have System Area { <i>area2</i> } as Prior Area.
CMR7017A	Area Config. Invalid Area { <i>area</i> } has both Next and Prior Areas the same.
CMR7018A	Area Config. Invalid Area { <i>area1</i> } has Next Area beyond first System Area { <i>area2</i> }.
CMR7019A	Area Config. Invalid System Area { <i>area1</i> } Next Area not next Area { <i>area2</i> } in chain.
CMR7020A	Area Config. Invalid System Area { <i>area1</i> } Prior Area not Prior Area { <i>area2</i> } in chain.
CMR7021A	Area Config. Invalid Starting Area { <i>area</i> } has broken froward chain to Final Area.
CMR7022A	Area Config. Invalid Area { <i>area</i> } has no backward chain to a Starting Subsystem Area.
CMR7023A	Area Config. Invalid Area { <i>area1</i> } has broken backward chain Prior Area { <i>area2</i> }.
CMR7024A	Area Already Defined Invalid Area { <i>area</i> } has already been defined for release { <i>release</i> }.
CMR7025A	Area Created Area { <i>area</i> } has been successfully created.
CMR7026A	Area Updated Area { <i>area</i> } has been successfully updated.

CMR7027A	Area deleted Area { <i>area</i> } has been successfully deleted.
CMR7028A	Areas Undefined Release { <i>release</i> } has no Areas defined.
CMR7029I	Areas Unblocked Area { <i>area</i> } is not blocked in Release { <i>release</i> }.
CMR7030I	Nothing In Progress Area { <i>area</i> } has nothing in progress at this time.
CMR7031I	No Resets Processed Area { <i>area</i> } had no in progress indicators selected for reset.
CMR7032I	In Progress Reset Area { <i>area</i> } in progress {??????} indicator reset.
CMR7033A	Undefined Entity Entity {??????} is not defined for {??????} rule contact Admin.
CMR7034I	Access Denied Access denied for entity {??????} for {??????} rule.
CMR7035I	Invalid Status Release { <i>release</i> } Area { <i>area</i> } has not been approved for check-off.
CMR7036I	Invalid Command Area package component test is only valid for system areas.
CMR7037I	Invalid Status Release { <i>release</i> } Area { <i>area</i> } has not been approved for check-in.
CMR7038I	Invalid Reason Diff version in final area; Check-in from package
CMR7039A	Invalid Status Clean-up of DEV packages not allowed; check release settings
CMR7040A	Invalid Status Clean-up of FRZ packages not allowed; check release settings
CMR7041A	Invalid Status Clean-up of APR packages not allowed; check release settings
CMR7042I	Invalid Status Only DEV, FRZ, and APR packages can be auto clean-up.
CMR7043I	Invalid Status Not all failed components can be selected for clean-up.
CMR7200I	Lock Not Found Area component lock(s) not found for specified lock.
CMR7201I	Duplicate Lock Duplicate area component lock found for {??????}.
CMR7202I	Locks Deleted Area component locks deleted for {??????}.

Release Packages Messages

CMR7500A	No Packages Release { <i>release</i> } has no packages attached.
----------	--

CMR7501I	Packages Found Release <i>{release}</i> still has packages attached.
CMR7502I	Pkg/Appl Match Error Package <i>{package}</i> does not match application <i>{application}</i> .
CMR7503I	Release Package Error Package <i>{package}</i> is not attached to Release <i>{release}</i> .
CMR7504I	Area Package Error Package <i>{package}</i> is not attached to Area <i>{area}</i> .
CMR7505I	Packages Found Release application <i>{application}</i> still has packages attached.
CMR7506I	Package Delete Error Package <i>{package}</i> is still attached to release <i>{release}</i> .
CMR7507I	Package Detached Package <i>{package}</i> is now detached from release <i>{release}</i> .
CMR7508I	Package Updated Package <i>{package}</i> is now attached to release <i>{release}</i> .
CMR7509I	No Releases Found No Releases found with Packages attached.
CMR7509I	No Releases Found No Releases found with Packages attached.
CMR7510I	Invalid Status Option only for Packages in DEV, FRZ or APR status.
CMR7511I	Audit Failure Package <i>{package}</i> failed the audit with a return code of <i>{returncode}</i> .
CMR7512I	Invalid Install Date Install date must be within release date <i>{date1}</i> to <i>{date2}</i> .
CMR7513I	Invalid Install Time Install time must be within release time <i>{time1}</i> to <i>{time2}</i> .
CMR7514I	Package not checked in Package <i>{package}</i> has not been checked into Release <i>{release}</i> .
CMR7515I	Package not Approved Package <i>{package}</i> has not been approved for Release <i>{release}</i> .
CMR7516I	Invalid Install info. Package <i>{package}</i> install outside release <i>{release}</i> install range.
CMR7517I	Component Checked In Component <i>{??????}</i> is checked into release <i>{release}</i> .
CMR7518I	Invalid Status Package <i>{package}</i> must be in <i>{??????}</i> status.
CMR7520I	Select Error Multiple selections not allowed, select only one.
CMR7530I	Attach Error Package attach halted by system exit, please contact administrator.

CMR7531I Detach Error | Package detach halted by system exit, please contact administrator.

Release Management General Services Messages

CMR8000I Process error | {??????} was not specified.

CMR8001I No Information | No information found for {??????} request.

CMR8002I Service completed | {??????} service completed

CMR8003I List continuing | The {??????} list is continuing.

CMR8240A Process Error | {??????} is already linked to {??????}.

CMR8240A Process Error | {??????} is already linked to {??????}.

CMR8490I Process Error | {??????} was not specified.

CMR8502I Process Error | {??????} is invalid.

CMR8600I List complete | The {??????} list is complete.

CMR8605I List continuing | The {??????} list is continuing.

CMR8646A Duplicate Record | Package Master record already exists

CMR8700I Service completed | {??????} service completed

CMR8701I Request pending | {??????} service request pending

CMR8702I Request Cancelled | {??????} service request cancelled

CMR8703I Service failed | {??????} service failed

CMR8730I Invalid input | Input field {??????} has invalid data: {??????}.

CMR8732I Service error | Data set information not available.

CMR8734I Service error | Unable to delete data set; Reason code = {??????}

CMR8750A Service error | Address space creation failed.

CMR8752I Record not found. | {??????} record not found.

CMR8756A Function restricted | Release LINKs restricted. Contact Local Admin.

CMR8758A Already Linked | LINK error - release {*release*} is already LINKed.

CMR8758A Already Linked | LINK error - release {*release*} is already LINKed.

CMR8760A Not Linked | UNLINK error - release {??????} is not LINKed.

CMR8764A Not Linked | Release {??????} is not Linked.

CMR8766A Linked Package | Release {??????} is Linked, process restricted.

CMR8785A Too much storage | Query results exhausted storage, query is too general.
Explanation: A release component query or search returned results that exceeded available storage.

Solution: Make the release component query or search more specific. Reduce the number of wild carded arguments or reduce the range of wild cards.

CMR8800I Invalid DSN Pattern | {??????} is an invalid DSN pattern for release datasets.

Release Management Query Messages

CMR9000A Application Error | Release Id {??????} application record not found in package master.

CMR9001A Invalid Date | {date} is an invalid Gregorian date for query component function.

CMR9002A Invalid Date Range | FROM date {date} is more current than the TO date for query component function.

CMR9003I No Components Found | No release components were found in this query.

Release Area Promotion Messages

CMR9500I Undefined Promotion | {??????} Promotion {??????} for {??????} is undefined.

CMR9501I Promotion Updated | Area Promotion {??????} has been successfully updated.

CMR9502A Promotion Deleted | Area Promotion {??????} has been successfully deleted.

CMR9503A Undefined Promotion | Application {application} has no promotion sites defined.

CMR9504A Undefined Promotion | Application {application} promotion site {site} has no promotion levels defined.

CMR9505A Promotion Defined | All promotion possible already defined for Area {area}.

CMR9506I Authorization Failed | Not allowed to promote/demote from site {site} level {??????}.

CMR9507I No Packages Selected | No packages were selected for processing.

CMR9508I No Packages Found | No release packages for {??????} for application {application}.

CMR9509I No Libraries Found | Application {application} has no promotion libraries for {??????}.

CMR9510I	No Promotion History No promotion history found for site <i>{site}</i> level <i>{??????}</i> .
CMR9511I	Invalid Date <i>{date}</i> is an invalid Gregorian date for <i>{??????}</i> function.
CMR9512I	Invalid Date Range FROM date <i>{date1}</i> is more current than the TO date <i>{date2}</i> .
CMR9513I	No Promotion History No component history found for site <i>{site}</i> level <i>{??????}</i> .
CMR9514I	No Overlays Found No Component overlays found for site <i>{site}</i> level <i>{??????}</i> .
CMR9515I	No Components Selected No Components were selected for processings.
CMR9516I	Promotion Submitted Area <i>{area}</i> promotion jobs submitted for <i>{??????}</i> .
CMR9517I	Demotion Submitted Area <i>{area}</i> demotion jobs submitted for <i>{??????}</i> .
CMR9518I	Demotion Submitted Package <i>{package}</i> demotion jobs submitted for <i>{??????}</i> .
CMR9519I	Components Disallowed Components selected can not be processed for this request.
CMR9520I	Package Promoted <i>{??????}</i> demotion <i>{??????}</i> release <i>{??????}</i> required.
CMR9521I	Package Not Promoted Package <i>{package}</i> is not promoted to any release sites.
CMR9522I	Demotion Required Demotion from <i>{??????}</i> required before promotion allowed.
CMR9523I	Demotion Required Demotion from <i>{??????}</i> required for unblock of area <i>{area}</i> .
CMR9523I	Demotion Required Demotion from <i>{??????}</i> required for unblock of area <i>{area}</i> .
CMR9524I	Demotion Required Demotion from <i>{??????}</i> required for <i>{??????}</i> .
CMR9525A	Promotion Defined All possible promotion already defined for Application <i>{application}</i> .
CMR9530I	Promotion Denied Promotion to <i>{??????}</i> must be done from ERO <i>{??????}</i> .
CMR9531I	Promotion Denied Promotion to <i>{??????}</i> must be done from ERO <i>{??????}</i> .
CMR9540I	Promotion Error All possible components already promoted to <i>{??????}</i> .

CMR9541I	Undefined Promotion Application Area Promotion for {??????} is undefined.
CMR9550I	Storage Error Memory unavailable for the {??????} Getmain RC { <i>returncode</i> }.
CMR9560I	Promotion Error Full Promotion not allowed to lower levels, use selective.
CMR9565I	Demotion Error All Packages not at level {??????} or 00, use selective demotion.
CMR9566I	Demotion Error Package not at selected level, use selective demotion.
CMR9567I	Demotion Error There is nothing to demotion, Package(s) are at level 00.
CMR9568I	Not Qualified No components selected for Promote qualify for area { <i>area</i> }.

Index

- checkout messages 14
- compare messages 21
- recompile messages 20
- stage messages 14
- assist messages 20
- guide to 4
- explanation
 - long 9
 - short 9
- browse log 30
- component
 - checkout 14
 - compare 21
 - recompile 20
 - stage 14
- DB2
 - assist 20
- descriptions 9
- general 10
- list 29
- package
 - approval 21
 - audit 19
 - backout 27
 - create 13
 - delete 25
 - freeze 21
 - promote 22
 - revert 25
- query 30
- release management administration 10
- release management general 9
- super/complex package 12
- approval messages 21
- audit messages 19
- backout messages 27
- create messages 13
- delete messages 25
- freeze messages 21
- promote messages 22
- revert messages 25
- messages 30

A

- action messages 10
- Adobe Acrobat 7
- audit messages 20

B

- browse log messages 31

C

- CMR0000A 10
- CMR0001I 10
- CMR0002I 10
- CMR0003A 10
- CMR0004I 10
- CMR0005I 11
- CMR0006A 11
- CMR0007A 11
- CMR0008A 11
- CMR0009A 11
- CMR0010A 11
- CMR0011A 11
- CMR0012A 11
- CMR0012I 11
- CMR0013I 11
- CMR0014I 11
- CMR0050A 11
- CMR0500A 11
- CMR0501A 11
- CMR0502A 11
- CMR0503A 11
- CMR0504A 11
- CMR0505A 11
- CMR0506A 11
- CMR0507A 11
- CMR0510A 11
- CMR0511A 12
- CMR0512A 12
- CMR0513A 12
- CMR0515A 12
- CMR0516A 12
- CMR0517A 12
- CMR0518I 12
- CMR0519A 12
- CMR0520A 12

CMR0521A 12	CMR2512A 15
CMR0522A 12	CMR2513I 15
CMR0523A 12	CMR2514A 16
CMR0524A 12	CMR2515A 16
CMR0525A 12	CMR2516A 16
CMR0526A 12	CMR2517A 16
CMR0527A 12	CMR2518A 16
CMR0528A 12	CMR2519A 16
CMR0529A 12	CMR2520A 16
CMR0530A 12	CMR2521A 16
CMR0531I 12	CMR2522A 16
CMR0532A 12	CMR2523A 16
CMR0533A 13	CMR2524A 16
CMR0534A 13	CMR2525A 16
CMR0535A 13	CMR2526I 16
CMR0536A 13	CMR2527I 16
CMR0537A 13	CMR2528I 16
CMR0538A 13	CMR2529I 16
CMR0539A 13	CMR2530I 16
CMR0540A 13	CMR2531A 16
CMR0541A 13	CMR2532A 16
CMR0542A 13	CMR2533I 16
CMR1000I 13	CMR2534I 17
CMR1001I 13	CMR2535A 17
CMR1002I 13	CMR2536A 17
CMR1003I 13	CMR2537A 17
CMR1004A 13	CMR2538A 17
CMR1005I 14	CMR2539A 17
CMR1006I 14	CMR2540A 17
CMR1066I 14	CMR2541A 17
CMR1090A 14	CMR2542A 17
CMR1094A 14	CMR2543A 17
CMR1500A 14	CMR2544A 17
CMR1501I 14	CMR2545I 17
CMR1502I 14	CMR2546A 17
CMR1503I 14	CMR2547A 17
CMR1504A 14	CMR2548A 17
CMR1505A 14	CMR2549A 17
CMR1506I 14	CMR2550A 17
CMR1507I 14	CMR2551A 17
CMR1527I 15	CMR2552A 17
CMR2000I 15	CMR2553A 17
CMR2001I 15	CMR2554A 18
CMR2002I 15	CMR2555A 18
CMR2500A 15	CMR2556A 18
CMR2501A 15	CMR2557A 18
CMR2502A 15	CMR2558A 18
CMR2503A 15	CMR2559A 18
CMR2504A 15	CMR2560A 18
CMR2505A 15	CMR2561A 18
CMR2506A 15	CMR2562A 18
CMR2507A 15	CMR2563A 18
CMR2508A 15	CMR2564A 18
CMR2509A 15	CMR2565A 18
CMR2510A 15	CMR2566I 18
CMR2511A 15	CMR2567I 18

CMR2568A 18	CMR4008A 21
CMR2569A 18	CMR4009I 21
CMR2570A 18	CMR4010A 21
CMR2571A 18	CMR4011A 21
CMR2572A 18	CMR4012A 21
CMR2573A 18	CMR4013I 21
CMR2574A 18	CMR4014I 21
CMR2575A 19	CMR4020I 21
CMR2576A 19	CMR4030I 21
CMR2577A 19	CMR4031I 22
CMR2578A 19	CMR4040I 22
CMR2579I 19	CMR4210A 22
CMR2580A 19	CMR4400I 22
CMR2581A 19	CMR4401I 22
CMR2582A 19	CMR4402I 22
CMR2583A 19	CMR4500I 22
CMR2584A 19	CMR4501I 22
CMR2585I 19	CMR5051A 22
CMR2586A 19	CMR5052I 22
CMR2587A 19	CMR5500A 22
CMR2588A 19	CMR5501A 22
CMR2589A 19	CMR5502A 22
CMR2590A 19	CMR5503I 22
CMR2591A 19	CMR5504I 22
CMR2592A 19	CMR5505I 22
CMR2593A 19	CMR5506I 22
CMR2594A 20	CMR5507I 23
CMR2595A 20	CMR5508A 23
CMR2596I 20	CMR5509A 23
CMR2597I 20	CMR5510A 23
CMR2598A 20	CMR5511A 23
CMR2599I 20	CMR5512A 23
CMR2600I 20	CMR5513A 23
CMR2601A 20	CMR5514A 23
CMR2602A 20	CMR5515A 23
CMR2610I 20	CMR5516A 23
CMR2700I 20	CMR5517A 23
CMR2701I 20	CMR5518A 23
CMR2702I 20	CMR5519A 23
CMR2730I 20	CMR5520I 23
CMR2731I 20	CMR5521I 23
CMR2800I 20	CMR6000A 23
CMR3000A 20	CMR6001A 23
CMR3001A 20	CMR6002A 23
CMR3050I 20	CMR6010A 23
CMR3292I 20	CMR6011I 23
CMR3500I 21	CMR6012I 24
CMR3501A 21	CMR6013I 24
CMR4000A 21	CMR6014I 24
CMR4001I 21	CMR6015I 24
CMR4002A 21	CMR6016I 24
CMR4003I 21	CMR6017I 24
CMR4004A 21	CMR6018I 24
CMR4005A 21	CMR6019I 24
CMR4006A 21	CMR6020I 24
CMR4007A 21	CMR6021I 24

CMR6022I 24	CMR7011A 27
CMR6023I 24	CMR7012A 27
CMR6024I 24	CMR7013A 27
CMR6025A 24	CMR7014A 27
CMR6026A 24	CMR7015A 27
CMR6027A 24	CMR7016A 27
CMR6028A 24	CMR7017A 27
CMR6029A 24	CMR7018A 27
CMR6030A 24	CMR7019A 27
CMR6031A 24	CMR7020A 27
CMR6032A 24	CMR7021A 27
CMR6033A 25	CMR7022A 27
CMR6034A 25	CMR7023A 27
CMR6035I 25	CMR7024A 27
CMR6036I 25	CMR7025A 27
CMR6037I 25	CMR7026A 27
CMR6038I 25	CMR7027A 28
CMR6039I 25	CMR7028A 28
CMR6040I 25	CMR7029I 28
CMR6041I 25	CMR7030I 28
CMR6042I 25	CMR7031I 28
CMR6043I 25	CMR7032I 28
CMR6044I 25	CMR7033A 28
CMR6045I 25	CMR7034I 28
CMR6046I 25	CMR7035I 28
CMR6047I 25	CMR7036I 28
CMR6048I 25	CMR7037I 28
CMR6049I 25	CMR7038I 28
CMR6050I 25	CMR7039A 28
CMR6051I 25	CMR7040A 28
CMR6052I 25	CMR7041A 28
CMR6500A 26	CMR7042I 28
CMR6502I 26	CMR7043I 28
CMR6503A 26	CMR7200I 28
CMR6504I 26	CMR7201I 28
CMR6507A 26	CMR7202I 28
CMR6508A 26	CMR7500A 28
CMR6509I 26	CMR7501I 29
CMR6510A 26	CMR7502I 29
CMR6511A 26	CMR7503I 29
CMR6512A 26	CMR7504I 29
CMR6513A 26	CMR7505I 29
CMR6514A 26	CMR7506I 29
CMR6515I 26	CMR7507I 29
CMR6516I 26	CMR7508I 29
CMR7000A 26	CMR7509I 29
CMR7001I 26	CMR7510I 29
CMR7002I 26	CMR7511I 29
CMR7003I 26	CMR7512I 29
CMR7004A 26	CMR7513I 29
CMR7005A 26	CMR7514I 29
CMR7006A 27	CMR7515I 29
CMR7007A 27	CMR7516I 29
CMR7008A 27	CMR7517I 29
CMR7009A 27	CMR7518I 29
CMR7010A 27	CMR7520I 29

CMR7530I 29
CMR7531I 30
CMR8000I 30
CMR8001I 30
CMR8002I 30
CMR8003I 30
CMR8100A 30
CMR8240A 30
CMR8490I 30
CMR8502I 30
CMR8600I 30
CMR8605I 30
CMR8646A 30
CMR8700I 30
CMR8701I 30
CMR8702I 30
CMR8703I 30
CMR8730I 30
CMR8732I 30
CMR8734I 30
CMR8750A 30
CMR8752I 30
CMR8756A 30
CMR8758A 30
CMR8760A 30
CMR8764A 30
CMR8766A 30
CMR8785A 31
CMR8800I 31
CMR9000A 31
CMR9001A 31
CMR9002A 31
CMR9003I 31
CMR9500I 31
CMR9501I 31
CMR9502A 31
CMR9503A 31
CMR9504A 31
CMR9505A 31
CMR9506I 31
CMR9507I 31
CMR9508I 31
CMR9509I 31
CMR9510I 32
CMR9511I 32
CMR9512I 32
CMR9513I 32
CMR9514I 32
CMR9515I 32
CMR9516I 32
CMR9517I 32
CMR9518I 32
CMR9519I 32
CMR9520I 32
CMR9521I 32
CMR9522I 32

CMR9523I 32
CMR9524I 32
CMR9525A 32
CMR9530I 32
CMR9531I 32
CMR9540I 32
CMR9541I 33
CMR9550I 33
CMR9560I 33
CMR9565I 33
CMR9566I 33
CMR9567I 33
CMR9568I 33
component
 checkout messages 15
 compare messages 22
 recompile messages 21
 stage messages 15

D

DB2
 assist messages 21
descriptions of messages 10
documentation
 guide to 5

G

general messages 11

H

help key 10

I

informational messages 10

L

list messages 30
long message explanation 10

M

manuals, information about 5
message
 explanation
 long 10
 short 10

messages

- browse log 31
- component
 - checkout 15
 - compare 22
 - recompile 21
 - stage 15
- DB2
 - assist 21
- descriptions 10
- general 11
- list 30
- package
 - approval 22
 - audit 20
 - backout 28
 - create 14
 - delete 26
 - freeze 22
 - promote 23
 - revert 26
- query 31
- release management administration 11
- release management general 10
- super/complex package 13

O

- online documentation 7

P

package

- approval messages 22
- audit messages 20
- backout messages 28
- create messages 14
- delete messages 26
- freeze messages 22
- promote messages 23
- revert messages 26

Q

query

- messages 31

S

- short message explanation 10
- super/complex package messages 13